SIC

a GILDAS working group software

February 7, 2002

SIC
Sympathetic Interpretor of Commands
Sympathique Interpréteur de Commandes
Version 7.0

The GILDAS working group is a collaborative project of the Observatoire de Grenoble (1,3) and IRAM (2), and comprises: F. Badia[2], D. Broguière[2], G. Buisson[1], L. Desbats[1], G. Duvert[1], T. Forveille[1], R.Gras[3], S. Guilloteau[1,2], R. Lucas[1,2], R. Neri[2] and P. Valiron[1].

(1) Laboratoire d'Astrophysique
Observatoire de Grenoble
BP 53 X
414 Rue de la Piscine
F-38402 Saint Martin d'Hères CEDEX

(2) Institut de Radio Astronomie Millimétrique
300 Rue de la Piscine
F-38406 Saint Martin d'Hères

(3) CEPHAG
Observatoire de Grenoble
F-38402 Saint Martin d'Hères CEDEX

Contributions from and invaluable discussions with J. Cernicharo, P. Begou[3], S. Delahaye[3], A. Dutrey[1,2], C. Kahane[1], P. Monger, J.L. Monin[1] and all **GILDAS** users are gratefully acknowledged.

Contents

1 Introduction **4**

2 The SIC Monitor **5**
2.1 Basic Features . . . 5
2.1.1 Syntax . . . 5
2.1.2 The Prompt . . . 6
2.1.3 The on-line HELP . . . 6
2.1.4 The Stack . . . 6
2.1.5 Line Editing Facility . . . 7
2.1.6 The Log File . . . 7
2.1.7 Symbols . . . 8
2.2 Variables and Expressions . . . 8
2.2.1 Definitions and Assignments . . . 8
2.2.2 Functions and Operators . . . 9
2.2.3 Vector Operations . . . 10
2.2.4 Implicit Loops . . . 10
2.2.5 Conditional Assignment . . . 11
2.2.6 Size casting . . . 11
2.2.7 GILDAS Images . . . 11
2.2.8 GILDAS Headers . . . 12
2.2.9 Character Variables and Implicit Formatting . . . 13
2.2.10 Initializing variables from external files . . . 14
2.3 SIC as a programming language . . . 14
2.3.1 Procedures (or Command Files) . . . 14
2.3.2 Loops . . . 15
2.3.3 Structured Programming and Logical Expressions . . . 15
2.3.4 Execution Level . . . 16
2.3.5 Error Recovery . . . 17
2.4 The **GUI** ("**G**raphics-**U**ser-**I**nterface") Mode . . . 18
2.4.1 Detached menus . . . 18
2.4.2 Assigning variables in "Window" mode . . . 19
2.4.3 Actions and Buttons in "Window" mode . . . 19
2.4.4 Help file structure . . . 20
2.5 Interacting with the Operating System . . . 20
2.5.1 File Operations . . . 21
2.5.2 SYSTEM command: VMS Version . . . 21
2.5.3 SYSTEM Command: Unix operating system . . . 22
2.6 Customizing . . . 22
2.6.1 Logical Names . . . 22
2.6.2 User Defined Commands . . . 22
2.6.3 Initialization File . . . 22
2.6.4 The SIC Command . . . 23

3 SIC Language Internal Help **24**
3.1 ACCEPT . . . 24
3.1.1 ACCEPT /ARRAY . . . 24
3.1.2 ACCEPT /BINARY . . . 24
3.1.3 ACCEPT /COLUMN . . . 24
3.1.4 ACCEPT /FORMAT . . . 24
3.1.5 ACCEPT /LINE . . . 25
3.2 @ . . . 25
3.3 BEGIN . . . 25

3.4 BREAK . . . 25
3.5 COMPUTE . . . 26
3.6 CONTINUE . . . 27
3.7 SYSTEM . . . 27
3.7.1 SYSTEM VMS . . . 27
3.7.2 SYSTEM UNIX . . . 28
3.8 DEFINE . . . 28
3.8.1 DEFINE CHARACTER . . . 29
3.8.2 DEFINE COMMAND . . . 29
3.8.3 DEFINE DOUBLE . . . 29
3.8.4 DEFINE FITS . . . 29
3.8.5 DEFINE FUNCTION . . . 30
3.8.6 DEFINE HEADER . . . 30
3.8.7 DEFINE IMAGE . . . 31
3.8.8 DEFINE INTEGER . . . 32
3.8.9 DEFINE LOGICAL . . . 32
3.8.10 DEFINE REAL . . . 32
3.8.11 DEFINE STRUCTURE . . . 32
3.8.12 DEFINE TABLE . . . 32
3.8.13 DEFINE /LIKE . . . 33
3.9 DELETE . . . 33
3.10 EDIT . . . 33
3.11 ELSE . . . 34

4 SIC Programming Manual 35

5 SIC Error Messages and Recovery Procedures 36
5.1 A through C . . . 37
5.2 D . . . 37
5.3 E . . . 39
5.4 F . . . 40
5.5 G . . . 42
5.6 H . . . 42
5.7 I . . . 42
5.8 J trough L . . . 44
5.9 M . . . 45
5.10 O through R . . . 47
5.11 S . . . 49
5.12 T . . . 52
5.13 U through Z . . . 52

1 Introduction

SIC (*) is a command line interpretor, written in FORTRAN and callable as a subroutine by any program. It provides a command language rather similar to the VAX-VMS DCL language, with the following major features:

- resolution of command abbreviations
- definition of symbols
- macro capabilities with arguments substitution during execution
- log file
- multi-language structure
- loop buffers for repetitive actions
- variables, arithmetic and logical expressions evaluation
- structured logical tests
- error recovery
- stack buffer
- keypad editing of command lines on VT200 compatible devices
- **NEW!: GUI interface on Motif systems**

This manual contains several chapters. Chapter 2 (The SIC monitor) should be read by every user before using **SIC**. Chapter 3 contains a copy of the internal help files of **SIC**. Chapter 4 is a programming manual for the user who would like to use **SIC** to create its own application. Chapter 5 is a list of all possible **SIC** error messages and of their most usual recovery procedures. This reference may be useful if you encounter an error message which you do not understand while running **SIC**.

2 The SIC Monitor

2.1 Basic Features

2.1.1 Syntax

All commands parsed by SIC must have the following syntax:
`[LANG\]COMM [ARG1 [ARG2 [...]]]  [/OPT1 [ARG11 [...]]]  [/OPT2 [...]]`

Where `LANG` is the language name, `COMM` the command name, `OPT1` and `OPT2` are option names, `ARGs` are the arguments of command and options, and brackets indicate optional fields.

The language, command and option names can be abbreviated and **SIC** checks for ambiguities. Arguments are separated by any number of separators (Blanks or Tabs). An option is a word beginning with a Slash. The options, like the commands, may have arguments. The syntax analyzer converts to upper case letters, strips useless separators, translate the symbols (See 2.5), expands the command and option names by looking through its current "dictionary".

The language field is optional. If present, it restricts the resolution of command name abbreviations to all languages of which it is an abbreviation. Otherwise, all languages are searched for.

The first action of the syntax analyzer is to suppress redundant separators. This is of course not always wanted (e.g. a figure caption) and **SIC** offers one way to circumvent this problem: the so-called strings, which are arguments included between double quotes ("). Strings are not modified by the syntax analyzer, but the outer double quotes will be ignored when the argument is used. However, strings are not protected against symbol substitution.

The program calling **SIC** may expect arguments of various types: character strings, real numbers, integers or logicals. For a specified type, e.g. a real number, the argument can be either a constant value (e.g. 3.14159), a variable (e.g. PI), or an expression (e.g. 2*ASIN(-1.0)). Conversion to the specified type is done automatically if possible at all (See 2.13).

A "-" sign as the last significant character in a command line indicates that a continuation follows on the next line (as in `DCL` command language) e.g.

```
SIC> HELP -
SIC> EDIT
```

is interpreted as

```
SIC> HELP EDIT
```

No special procedure is used to cut strings for continuation lines. It is simply done according to the following example

```
SIC> LABEL "A very long-
SIC>  string must be cut"
```

which is interpreted as

```
SIC> LABEL "A very long string must be cut"
```

Comments may appear at the end of any line. The comment area starts with a "!" sign; all the following text is ignored. Comments can be used in conjunction with the continuation mark :

```
SIC> DRAW RELOCATE 13-       !This is an example of comments
SIC> .45 15.00 /USER         ! and continuation
```

is interpreted as

```
SIC> DRAW RELOCATE 13.45 15.00 /USER
```

BUT do not try this one

```
SIC> LABEL "A lon-    ! A long string
SIC> g caption"       ! with continuation mark
```

which produces the message

```
E-INTER,  Unbalanced quote count
```

immediately after the first line as been typed in, because the syntax analyzer was considering the - and ! signs as part of a string. Comments may be convenient to self-document complex procedures.

2.1.2 The Prompt

The prompt is defined by the calling program. In addition, **SIC** modifies the prompt aspect according to the execution level. In this example the calling program is assumed to pass the string `'GAG'` to **SIC**. Then the following prompts may appear :

```
GAG>     ! Lowest execution level
GAG_3>   ! Third execution level
GAG_5:   ! Compile mode for the Loop buffer at level 5
```

2.1.3 The on-line HELP

The `HELP` utility of **SIC** is structured at three different levels. Without an argument, `HELP` gives the list of available help. Since **SIC** is a multi-language system, `HELP Language_Name\` prints one line description of all commands of the named language. For example, `HELP SIC\` gives a one line description of all the **SIC** monitor commands. `HELP Command_Name` prints more detailed information on that command. For some command, the help text is divided in subtopics which can be accessed by typing `HELP Command_Name Subtopic`.

If you consult a long `HELP` text, you may use the `PAGE` mode. You will then be prompted for continuation when the screen is full. The page mode is usually set by default on "intelligent" terminals, and you can switch between `PAGE` and `SCROLL` mode for the help using command

```
SIC> SIC HELP PAGE     or     SIC HELP SCROLL
```

On-line access to the documentation can be obtained by

```
SIC> SIC HELP CONTENT  or     SIC HELP INDEX
```

In `CONTENT` mode, `HELP Command` displays the documentation page indicated for the specified `Command` by the table of content, while in `INDEX` mode, the first page indicated in the index is displayed.

2.1.4 The Stack

The Stack is an internal buffer where commands are automatically placed. It may be considered as a real time logfile, from which you can retrieve commands. The stack buffer may contain up to 300 commands, less if the commands are very long. It is organized as a circulating buffer, with a `"first in - first out"` replacement procedure when the buffer is full, or when the maximum number of commands is reached. The command number always increase, even when the buffer fills up.

The command

```
RECALL [Arg]
```

recalls command from the stack for execution. Depending on whether line editing mode is possible (see keypad line editing), the recalled command may be edited prior to submission, or not. If no argument is present, the last command is recalled. If the argument is a number N, the N-th command of the stack is recalled. If the argument is a string, the stack is scanned backwards to find a command beginning by this string.

If line editing is possible, commands may also be retrieved from the stack using the Up and Down arrows on the terminal keyboard. However to bypass `VMS` line editing, you must strike GOLD (`<PF1>`) key first.

The command

```
EDIT
```

without arguments will dump the stack on a file named `STACK.DefExt` (where `DefExt` is the current default procedure extension), and calls the default editor to edit this file. It can then be executed as any other procedure.

2.1.5 Line Editing Facility

Line editing is normally available to edit command lines prior to submission. The following control keys can be used

```
<^A>            Move to beginning of line
<^B>            Backspace one character (BACKWARD)
<^F>            Advance one character (FORWARD)
<^H>            Delete previous character (BACKSPACE)
<^J>            Delete to beginning of word, or previous word
<^M>            Submit command line (RETURN key)
<^N>            Recover Next command
<^P>            Recover Previous command
<^U>            Delete to beginning of line
<DEL>           Delete previous character
```

These commands are identical to the standard line editing in the Emacs editor.

If you are using an ANSII compatible terminal (VT100 series and upwards), the numeric keypad is also available to perform additional actions

```
<PF4>           Delete to end of line
<->             Delete to end of word, or next word
<LF>            Delete to beginning of word, or previous word
<,>             Delete character
<DEL>           Delete previous character
<1>             Move to next word
<2>             Move to end of line
<4>             Set advance mode (for WORD moves)
<5>             Set backup mode (for WORD moves)
<ENTER>         Submit the command line
<RETURN>        Same as above
<Up Arrow>      Retrieve previous command of Stack
<Down Arrow>    Retrieve next command of Stack
<Left Arrow>    Backward one character
<Right Arrow>   Advance one character
```

These commands are the same as in the EDT Digital text editor, except for Backspace (Ĥ).

For lines longer than the screen width, the display uses a window and automatically centers it on the current character when the cursor position reaches one end.

Note that on VMS operating systems, this editing mode somehow conflicts with the basic DEC line editing facility, in the sense that the DEC editing facility has priority over it. To access to the keypad editing mode you should press the GOLD (`<PF1>`) key. Otherwise, the Up and Down arrows will only allow you to retrieve the last typed line (default DEC line editing).

The keypad editing mode can be turned off by the `SIC EDIT OFF` command and turned on by the `SIC EDIT ON` command. Line editing mode affects the error recovery system and the RECALL command.

2.1.6 The Log File

The *Log File* is a post-mortem listing of all commands issued and successfully executed during a working session. It is kept on leaving **SIC** (by using `EXIT`). Some commands like `HELP` are not put into the *Log File*. Most programs using **SIC** put the *Log File* in the `GAG_LOG:` area (usually your default directory, but

see "Customizing") to avoid multiplication of files in a directory tree, and purge it upon exit keeping the last two or three versions. *Log Files* can be used as the basis of subsequent procedures. If you are short of disk space, purge and delete yourself the log files.

2.1.7 Symbols

SIC allows the user to define symbols, which are abbreviations of any character string. Any command line is first parsed for symbols in the symbol table. The command interpretor assumes that the following entities may be symbols :

- the first word of command line (e.g. `AA` in command `AA /OPTION`)
- any string (without spaces) included between single quotes (e.g. `'AA'`). This syntax may also indicate a character variable (See "Character Variables and Implicit Formatting").

There is no recursive analysis of the line for the symbol translation. Note that, contrary to character variables, the symbol translation occurs even within strings, and that case does not matter.

Symbols are defined by issuing the following command

```
SIC> SYMBOL TOTO "Whatever you want"
```

A symbol definition may refer to an other already defined symbol. Whenever `'TOTO'` is found in a command line, it will be replaced by the string Whatever you want e.g.

```
SIC> LABEL "Units 'TOTO'"
```

will be interpreted as

```
SIC> LABEL "Units Whatever you want"
```

The Symbol Table can be listed using command `SYMBOL` without arguments. If `SYMBOL` has a symbol name for argument, the translation of this symbol is given. `DELETE /SYMBOL TOTO` will delete symbol `TOTO` from the current symbol table. Note that symbols should only include alphanumeric characters.

2.2 Variables and Expressions

Most of the power of **SIC** comes from its ability to handle variables and perform operations (arithmetic or logical) on them. When used in combination with the **GreG** program for display, **SIC** variables can be used to performed efficient data analysis.

2.2.1 Definitions and Assignments

SIC supports variables and arithmetic or logical expressions evaluation. Variables can be defined either by the program or by the user. Program-defined variables may have the Read-Only attribute which prevents them from being overwritten by the user (see **SIC** PROGRAMMING MANUAL). Variable names are up to 15 characters long, upper case only, and must begin with a letter. A variable can be LOCAL or GLOBAL. GLOBAL variables are valid at any execution level in **SIC**. On the opposite, LOCAL variables are valid only in the procedure where they have been declared, or in any loop started within this procedure, or in any interactive level generated from this procedure (by a `PAUSE` or an error). Variables declared by a program are always GLOBAL.

Arithmetic and logical expressions are automatically evaluated when used as arguments to commands. The evaluation is done in single or double precision arithmetic, according to command `SIC PRECISION`. Parentheses are allowed, but there is a limit on the complexity of arithmetic and logical expressions. A local variable has precedence over a global variable of the same name. Local variables are deleted when the creating procedure terminates.

Variables may be defined using command `DEFINE`, and assigned values using command `LET`. **SIC** is a declarative language in which all variables must be defined before being used. For convenience, command `LET` has an option `/NEW` which allows declaration of the assigned variable. Five type of variables are allowed : `REAL, INTEGER, LOGICAL, DOUBLE` (for double precision real variables), and `CHARACTER`.

Variable values may be typed using the `EXAMINE` command, which also indicates whether the variable is GLOBAL or LOCAL, and in the latter case, the corresponding procedure level.

2.2.2 Functions and Operators

For arithmetic expressions, the known operators are

```
-          Subtraction
+          Addition
*          Multiplication
/ or |     Division (the | sign has been added because the /
                   is the option separator)
** or ^    Exponentiation
```

Known single argument functions are

```
ABS        Absolute value
ACOS       Arc Cosine
ASIN       Arc Sinus
ATAN       Arc Tangent
COS        Cosine
COSH       Hyperbolic Cosine
EXP        Exponential
INT        Integer Part
LOG        Natural logarithm
LOG10      Decimal Logarithm
NINT       Nearest Integer
SIN        Sinus
SINH       Hyperbolic Sinus
SQRT       Square Root
TAN        Tangent
TANH       Hyperbolic Tangent
```

Known two arguments functions are

```
ATAN2    Arc tangent with two arguments
MAX      Maximum of two values
MIN      Minimum of two values
MOD      Modulo (true modulo, even for negative numbers)
SIGN     Sign transfer
```

For logical expressions, the known operators are

```
.OR.       .AND.      .NOT.
.GT.       .GE.       .LT.       .LE.
.NE.       .EQ.
```

and the known functions are

```
EXIST    Returns .TRUE. if its argument is a defined variable
FILE     Returns .TRUE. if its argument is an existing file.
```

Additional arithmetic functions may be declared by the calling programs. Two special functions are always declared :

```
NOISE(x)      Gaussian Noise of Sigma X
RANDOM(x)     Random Number between 0 and X
```

These additional functions, and their number of arguments, can be listed using command `EXAMINE /FUNCTION`.

2.2.3 Vector Operations

SIC supports *array variables* of up to 4 dimensions. Array dimensions are specified between brackets (not parentheses) with the comma as separators. `CHARACTER` and `LOGICAL` variables can also be arrays. Arithmetic operations always work on arrays on an element by element basis. Scalar variables are considered like arrays of any size. For example,

```
DEFINE REAL A[5] B[5]
LET A = ABS(B)
LET B = 1.0
```

assigns to each element of A the absolute value of the corresponding element of B, and then assigns to each element of B the value 1.0. Dimensions of arrays must match in arithmetic expressions.

Any subset of an array variable can be referenced in an expression, for example

```
DEFINE REAL A[5] B[5,10] C[5,10,3]
LET B[,6] = A
LET C[,10,1] = B[,3]
```

Dimensions of the sub-arrays must also match. Transposition is now supported : e.g. in the precedent example, C[1,,1] could have replaced C[,10,1]. The indices can be previously defined scalar variables. Leading commas may be omitted.

```
DEFINE REAL A[5] B[5,10] C[5,10,3]
LET B[,6] = A
LET C[,10,1] = B[,3]
```

It is also possible to specify a range of indexes rather than a single index.

```
DEFINE REAL A[5] B[3,10] C[4,4,4]
LET B[,6] = A[2:4]
LET A[:3] = B[,8]
LET A[2:5] = C[3,,4]
```

2.2.4 Implicit Loops

It is sometimes convenient to assign to an array values which are functions of the array indices. This can be done using "implicit loops", such as

```
DEFINE REAL A[10,10]
LET A[I,J] = EXP(-((I-5)|2)**2-((J-6)|3)**2)
```

in which I and J have NOT been declared as known variables. I and J are known as "implicit variables". The preceding expression is equivalent to the following commands

```
DEFINE REAL A[10,10]
FOR J 1 TO 10
FOR I 1 TO 10
LET A[I,J] = EXP(-((I-5)|2)**2-((J-6)|3)**2)
NEXT
NEXT
```

but it executes thousands of times faster... Mixing of implicit and declared (or loop) variables is strictly forbidden at present. It can usually be avoided by using intermediate arrays.

2.2.5 Conditional Assignment

Another convenient function is to assign to an array new values only in for some parts of the array, based on a logical mask or logical expression. The option `/WHERE` of command `LET` allows such operations. For example

```
DEFINE REAL A[10,10]
LET A[I,J] = EXP(-((I-5)|2)**2-((J-6)|3)**2) /WHERE (I+J).LT.10
```

will set only a part of the A array (note that I and J are "implicit variables").

The preceding expression is equivalent to the following commands

```
DEFINE REAL A[10,10]
FOR J 1 TO 10
FOR I 1 TO 10
  IF (I+J).LT.10 THEN
    LET A[I,J] = EXP(-((I-5)|2)**2-((J-6)|3)**2)
  ENDIF
NEXT
NEXT
```

but it executes thousands of times faster...

Conditional assignment can be mixed with implicit loops, as shown above, but there are some syntax restrictions: please refer to the internal help for more details.

2.2.6 Size casting

Typing the explicit dimensions when declaring a new variable may be tedious. SIC allows to create arrays of dimensions identical to those of existing variables through the `/LIKE` option. For example, if A is an existing integer variable of dimensions 10,5,30 the following command

```
DEFINE REAL B C D /LIKE A
```

is equivalent to

```
DEFINE REAL B[10,5,30] C[10,5,30] D[10,5,30]
```

and defines three real arrays of dimension [10,5,30]. This feature, called size casting, is specially convenient to declare arrays that match images (see below).

2.2.7 GILDAS Images

Variables are normally allocated using virtual memory, and hence are lost once the program terminates. It is possible to allocate variables as disk files, called **Images**, which are mapped into the virtual memory of the program, using command

```
DEFINE IMAGE Variable File Keyword
```

where

`Variable` is the desired variable name. This variable name should be at most 3 characters to hold the header variables.

`File` is the name of the file holding the image. Default extension is `.GDF` (**GILDAS** Data Format), but any extension is valid.

`Keyword` indicates how the file must be used and may be

`READ` use an existing image as Read-Only variable

`WRITE` use an existing image as Read-Write variable. The user must have Write access to the file.

`EXTEND` Allows to extend the last dimension of an existing image. The user must have write access to it.

`REAL` create a new image of type `REAL`

`DOUBLE` create a new image of type `DOUBLE`

`INTEGER` create a new image of type `INTEGER`.

For already existing images (`READ, WRITE`), the type and size of variable are determined by the program. For new images, the size must be specified in the variable name, and the variable is always declared as Read-Write. To `EXTEND` image, the new value of the last dimension must be specified in the variable name. Header variables (see next section) are defined with the same status (Read or Write) as the image.

Images (i.e. files in the **GILDAS** data format) are used by most programs distributed by the Groupe d'Astrophysique. See the **GILDAS** (Grenoble Image and Line Data Analysis Software) documentation. **Tables** usually refer to images with 2 dimensions, but more generally to images which do not define a coordinate system.

The `DEFINE IMAGE` command has two variants, `DEFINE TABLE` and `DEFINE HEADER`. `DEFINE TABLE` only defines a single variable pointing to the image content. On the opposite `DEFINE TABLE` defines only the header variables, as described in next section.

2.2.8 GILDAS Headers

The `DEFINE IMAGE` command allows **SIC** to access not only to the content of an image (the data value), but also to all its associated parameters; `DEFINE HEADER` allows access only to these associated parameters. The header variables have names derived from the generic name by adding the special character % and an extension (such as e.g. `NDIM` for the number of dimensions) to the generic header name. For example, command `DEFINE HEADER VAR file.gdf READ` also creates the following variables:

```
VAR%GENE       Integer        Length of general section
VAR%NDIM       Integer        Number of dimensions (ReadOnly)
VAR%DIM        Integer[4]     Dimensions           (ReadOnly)
VAR%CONVERT    Double[3,4]    Conversion formulae for the 4 axes:
                              Reference pixel,
                              Value at reference pixel,
                              Increment
VAR%BLAN       Integer        Length of blanking section
VAR%BLANK      Real[2]        Blanking and tolerance
VAR%EXTREMA    Integer        Length of extrema section
VAR%MAX        Real           Maximum
VAR%MIN        Real           Minimum
VAR%WHERE      Integer[4,2]   Position of max and min
VAR%DESC       Integer        Length of units and system section
VAR%UNIT       Char*12        Image unit
VAR%UNIT1      Char*12        First axis type
VAR%UNIT2      Char*12        Second axis type
VAR%UNIT3      Char*12        Third axis type
VAR%UNIT4      Char*12        Fourth axis type
VAR%SYSTEM     Char*12        Coordinate system
VAR%POSI       Integer        Length of position section
VAR%SOURCE     Char*12        Source name
VAR%RA         Double         Right Ascension
VAR%DEC        Double         Declination
VAR%LII        Double         Galactic longitude
VAR%BII        Double         Galactic latitude
VAR%EPOCH      Real           Epoch of coordinates
VAR%PROJ       Integer        Length of projection section
```

```
VAR%PTYPE      Integer        Projection type (code)
VAR%A0         Double         first coordinate of projection center
VAR%D0         Double         second coordinate of projection center
VAR%ANGLE      Double         position angle of projection
VAR%X_AXIS     Integer        First projected axis
VAR%Y_AXIS     Integer        Second projected axis
VAR%SPEC       Integer        Length of spectroscopy section
VAR%LINE       Char*12        Line name
VAR%FREQRES    Double         Frequency resolution
VAR%FREQOFF    Double         Frequency offset
VAR%RESTFRE    Double         Rest Frequency
VAR%VELRES     Real           Velocity resolution
VAR%VELOFF     Real           Velocity offset
VAR%F_AXIS     Integer        Frequency/Velocity axis
VAR%BEAM       Integer        Length of beam section
VAR%MAJOR      Real           Major axis of beam
VAR%MINOR      Real           Minor axis of beam
VAR%PA         Real           Position angle of beam
```

`VAR` becomes a dummy variable of type header, which can only be referenced in a further `DELETE /VARIABLE` command. `VAR` can have at most 6 characters. The `VAR%item` variables are ReadOnly or ReadWrite according to the keyword following the filename, except for the dimension variables (`VAR%DIM` and `VAR%NDIM`), which cannot be modified.

Full headers can be copied to one another, using the command

```
LET A% = B%
```

which copies the header of image B into that of image A (dimensions are not modified, however). Thus a full copy of a **GILDAS** data file can be obtained within **SIC** as follows:

```
DEFINE IMAGE A Oldfile.gdf READ
READ DEFINE INTEGER N1 N2 N3 N4
LET N1 A%DIM[1]
LET N2 A%DIM[2]
LET N3 A%DIM[3]
LET N4 A%DIM[4]
DEFINE IMAGE B[N1,N2,N3,N4] Newfile.gdf REAL
LET B A      !  Copy A data into B
LET B% A%    ! Copy A header into B header
DELETE /VARIABLE B ! Deletes the SIC variables, but not the file...
```

A simpler way to declare new images is to use the size casting provided by the `/LIKE` option:

```
DEFINE IMAGE A Oldfile.gdf READ
DEFINE IMAGE B Newfile.gdf REAL /LIKE A  ! Define B like A...
LET B A      !  Copy A data into B
LET B% A%    !  Copy A header into B header
DELETE /VARIABLE B ! Deletes the SIC variables, but not the file...
```

2.2.9 Character Variables and Implicit Formatting

In contrast with the Symbols, which are substituted in the command line before the parsing, variables and expressions are evaluated after the command line analysis. In general, a real (resp. integer and logical) argument is considered as a mathematical (logical) expression and evaluated when read by the program calling **SIC**The command line stored in the stack and logfile contains the mathematic expression, not the current value.

The behaviour for Character variables is slightly different, in the sense that only items included between single quotes are considered as possible character variables, if they have not yet been expanded as known symbols of course. Using character variables in logical expressions is an exception to this rule because translation should be avoided in this case, see next chapter. Contrary to Symbols, Character variables translation does not occur in strings.

Not only Character variables but also any mathematical and logical expression may be included between quotes. Mathematical expressions are evaluated and formatted using the shortest possible format. Logical expressions are evaluated as YES or NO. The formatted command string is substituted to the expression and quotes, and used in the string returned as character argument to a command. This feature is known as "Implicit Formatting". In this way, non-character variables and expressions can be used where a character argument is required. The reverse is not true however: Implicit Formatting should not be used if a non-character argument is expected.

Any variable can be typed using the `EXAMINE` command which will display the variable name followed by its current value. More than one variable may be displayed at the same time using the `SAY` command.

Concatenation of variables is easily obtained by mixing explicit strings (between double-quotes) and implicitely formatted variables. For example, is A is character variable of content "I am", the following command

```
LET B "You know "'A'" happy"
```

attributes to B the content "You know I am happy".

2.2.10 Initializing variables from external files

SIC allows easy initialization of variable from files in "foreign" format (i.e. not **GILDAS** images). This can be done with the `ACCEPT` command, which allows reading variables from formatted or unformatted files. This command is available in 3 major modes

- `ACCEPT /ARRAY`
  `ACCEPT Var /ARRAY File [/FORMAT String] [/LINE Begin [End]]`
  reads in free format or user specified format variable `Var` from file `File`, selecting a line range if specified. `Var` may have up to 4 dimensions.

- `ACCEPT /BINARY`
  `ACCEPT Var /BINARY File [Skip]`
  reads the binary file `File` to set variable `Var`. `Skip` is a number of BYTEs to skip before reading. Note that there is no type conversion in this command: the binary content of the file must match the type declared for the variable.

- `ACCEPT /COLUMN`
  `ACCEPT V1 [V2 [...]] /COLUMN File [/FORMAT String] [/LINE Begin [End]]`
  reads the formatted file `File` to set one or several 1-dimensional variables `V1 V2 ...`. Free format is used by default, unless the `/FORMAT` option is specified. The special argument `*` can be used instead of the variable name to indicate a "dummy" variable, which is read from the file, but not assigned. This allows to skip a column in the input file.

2.3 SIC as a programming language

The second most important power of the SIC command language is its programming features. SIC supports command procedures, loops and conditional execution of statements in procedures.

2.3.1 Procedures (or Command Files)

SIC has command procedure capabilities. A procedure is an external file containing valid commands. The tokens &1, &2, ..., &8 can be used in the body of the procedure, and when a procedure is invoked its arguments will be substituted for these tokens. Substitution occurs also within the character strings. A procedure is executed by

```
SIC> @ Procedure_Name [P1,...]
```

Commands are read from the file Procedure_Name (with a default extension depending on the calling program or the user) and executed. P1 is a parameter string to be substituted to the token &1 during execution. Up to nine parameters may be passed to the procedure. The commands are echoed to the user's terminal if the `VERIFY` switch is set `ON`. Most programs using **SIC** define a default procedure extension equal to the program name (such as `.GREG, .CLASS, etc...`). If not specified, the default macro extension is `.PRO`. It can be listed and changed using command `SIC EXTENSION`.

Procedures (or any text file indeed) can be typed from within **SIC** using the command `TYPE`.

```
SIC> TYPE Procedure_Name
```

If no argument is given to `TYPE`, the stack buffer is listed.

2.3.2 Loops

```
FOR Variable List
```

opens a `FOR-NEXT` loop to be executed for values given in the list.

This command may have the following format :

```
FOR I n1 n2 n3 to n4 by n5 n6 to n7
```

where I is the loop variable name. Loop variables must not be previously defined, and are undefined when the loop execution is finished. The prompt changes to `'SIC_n: '`, where n is the current **SIC** execution level, and all subsequent commands until `NEXT` are the body of the loop. The loop variable can be used as any other **SIC** variable, e.g. in arithmetic expressions such as EXP(-(I+3.5)**2). In addition, it can be used in a formatted way when it is included between quotes, e.g. in `NAME.EXT;'I'`. In this case, the substitution occurs also within the character strings (see "Implicit Formatting"). The commands are echoed to the user's terminal if the `VERIFY` switch is set `ON`.

Up to 9 loop levels can be nested, and there is no restriction upon the loop and procedure nesting, e.g.

```
SIC> FOR I List1
SIC> FOR J List2
SIC> ..
SIC> NEXT
SIC> FOR J List3
SIC> ...
SIC> NEXT
SIC> NEXT
```

is perfectly valid.

```
FOR /WHILE Logical_Expression
```

This is another possible syntax for `FOR-NEXT` loops. The loop is executed conditionally provided "Logical_Expression" is `TRUE`. "Logical_Expression" must be any valid logical expression, possibly including arithmetic sub-expressions in it.

2.3.3 Structured Programming and Logical Expressions

SIC includes structured logical tests of the form

```
IF Logical_Expression [THEN]
  ...
ELSE IF Logical_Expression [THEN]
  ...
```

```
ELSE
  ...
ENDIF
```

The syntax is similar to FORTRAN with two major differences. First, the logical expression of an `IF` command cannot be followed by another command to be executed, and the `THEN` keyword is optional. Second, `ELSE` and `IF must` be separated by at least one space or tab in the `ELSE IF` command. Nesting of `IF` blocks up to 20 levels is allowed. In addition, provided the restriction on the number of loops, procedures and `IF` blocks is met, any nesting between loops, procedures and `IF` blocks is allowed.

Variables can appear in the logical expressions, and this is one of the most frequent use for variables. An `IF` block must be complete in a procedure or loop, otherwise an error occurs.

Logical expressions may include operations on arithmetic, logical or character variables. In logical expressions, strings (i.e. text included between double quotes) are recognized as character constants. Character variables should not be included between single quotes, since their current values would be substituted by **SIC** before logical expression analysis. Arithmetic sub-expressions are allowed.

Assuming `GOOD` is a character variable whose current value is `"Let it be"`, and `PI = 3.1415926535897932` (Double precision), examples of valid logical expressions are :

```
    L = ("I am happy".EQ.GOOD) (.FALSE.)

    L = ("Let it be".EQ.GOOD) (.TRUE.)

    L = ("I am happy".EQ."'GOOD'") (.TRUE.)
evaluated literally since GOOD is not substituted in a string

    L = PI.EQ.ACOS(-1.0) (.TRUE.)

    L = 'PI'.EQ.2*ASIN(1.0) (.FALSE.)
evaluated as 3.141592653589793.EQ.2*ASIN(1.0)
because of implicit formatting, one digit being lost in the
formatting because of binary to decimal conversion.

    L = ("I am happy".NE.GOOD).OR.(PI.EQ.ACOS(-1.0))
```

But the following expressions are invalid :

```
    L = (PI.EQ.GOOD) Variable type mismatch.

    L = ("I am happy".NE.'GOOD')
Because it is evaluated as ("I am happy".NE.Let it be).
```

2.3.4 Execution Level

Procedures and Loops can be nested. Hence, **SIC** may operate at different *Levels of Execution*. Commands are provided to activate some level (`@, FOR`), suspend (`PAUSE`), resume (`CONTINUE`) or abort its execution (`NEXT, QUIT, BREAK, RETURN`). Errors occuring within a non-interactive execution level generate a `PAUSE`, which returns interactive control to the user at a level immediately higher. The prompt at level I changes to `'SIC_I> '` to remind the user what **SIC** is doing.

It is also possible to interrupt a sequence of commands (procedure or loop) by pressing `<^C>` at any time. The current command is then normally completed (unless it traps the `<^C>` by itself), but a `PAUSE` is generated when the command terminates.

Related commands :

BREAK
: Aborts Loop execution without generating an error. The loop is considered to have completed successfully, and execution resumes at the command line following the NEXT command of the loop.

CONTINUE
: resumes Procedure or Loop execution after a `PAUSE`, either explicit or generated because of an error condition. *C is always a non ambiguous abbreviation of* `CONTINUE`, unless you redefine it as a Symbol.

EXIT
: exit from the program.

NEXT
: The effect of this command depends on the context:

  - If encountered while entering loop commands (during loop compilation), it ends the loop definition and activates its execution.
  - If encountered during loop execution, all commands left in the loop are skipped and loop execution starts again for next index value. This typically occurs when it is specified as error handling (`ON ERROR NEXT`), or typed interactively after a `PAUSE` has occured.

PAUSE
: sets a break point in the Loop or a Procedure. `PAUSE` returns control to the user when executed in any of the non-interactive modes (Loop and Procedures). Any valid command can be executed while in interrupt mode. The normal execution of the interrupted level can be resumed by typing `CONTINUE`. `NEXT` and `QUIT` may also be valid continuation sequences. The PAUSE command can be followed by a character string argument which is printed before the PAUSE becomes effective.

QUIT
: If `QUIT` is typed after a `PAUSE` occured in a Procedure or Loop, the execution of the interrupted procedure is aborted, and one returns to the previous level of execution. In this case, an error condition is transmitted to the previous level to allow the user to take the appropriate decision.

RETURN
: Terminates procedure execution, and returns to the previous level of execution. An implicit `RETURN` is always executed at the end of the command file. Command `RETURN BASE` returns to the normal interactive level (level 0). Command `RETURN ERROR` returns to the previous level of execution, but also transmit an error status to this level.

2.3.5 Error Recovery

SIC has a powerful error recovery system. Every command returns to the **SIC** monitor a status to indicate if any error occured. If so, by default **SIC** attempts to make a `PAUSE`. In an interactive session, there is a (presumably intelligent) user to decide what to do, and who can hopefully correct the error (a typing mistake for example) and then type `CONTINUE` to proceed. In a non-interactive session (Batch or command procedure), no such intelligent decision is possible and the `PAUSE` causes an Abort of the program.

If keypad edition is possible, the command which caused the error is automatically displayed for correction by the user. The prompt is put in inverse video to indicate that edition is going on. The corrected line will be submitted whenever `<RETURN>` or `<ENTER>` keys are pressed.

It is possible to override this default behaviour by command

```
ON ERROR [Other command]
```

After this command has been issued, any error will attempt to execute the `"Other command"`. If this command happens to fail, **SIC** will try to make a `PAUSE`. This command can be any command of the program, including `@, CONTINUE, EXIT, NEXT`. They will behave exactly has usual, except command `QUIT`.

In interactive mode, the `QUIT` command is usually typed to abort an erroneous procedure. In this case, it decreases the execution level by 2, and transmit an error to this new level to signal an abnormal end of some procedure. In error recovery mode, QUIT directly transmit the error to the previous level. It is in fact translated into RETURN ERROR.

Judicious use of the `ON ERROR` command may enable you to make batch jobs very conveniently. In particular, think of the behaviour of `ON ERROR NEXT` and `ON ERROR BREAK` when using loops, and `ON ERROR RETURN` when using procedures.

The ON ERROR command is a *local* command: that means it is only valid within the procedure which declared it (and loops executed within this procedure). However, if a PAUSE occured from a procedure (or loop), an interactive execution of the ON ERROR command will reset the error processing behaviour of the interrupted procedure.

2.4 The GUI ("Graphics-User-Interface") Mode

When a windowing system is available, **SIC** provides facilities (called GUI mode) to create documented input windows by which the user can modify variables and execute pre-defined commands. Currently, such facilities are available for Motif-based systems (soon for MAC-OS, and later for Windows-95).

SIC can create 3 types of windows:

- Detached menus
  which are menu bars created by the `GUI\PANEL /DETACH` command. These menus have no associated parameters, but run in parallel with the main program. Pre-defined commands are activated by pressing the various buttons.

- Main input window
  which is created by the `GUI\PANEL` command. The user can modify variables using widgets, and execute one or several actions by pressing the appropriate buttons. The variables are actually modified only when a button is pressed.

- Optional windows
  which are created by the `GUI\BUTTON` command. Such windows are a with a specific command, and are hidden by default. They are typically used to hold variables which are seldom modified by the user. The variables defined in these windows and in the main window are modified when the `GO` button is pressed.

User input with this system is fairly intuitive. Help is available by clicking on the help button(s) or on the prompt area for each variable.

The following description rather concerns advanced users who want to create their own window interfaces.

2.4.1 Detached menus

Detached menus are created using the `GUI\PANEL /DETACH` command. Once created, buttons and pulldown menus can be defined within the detached menu using respectively the `GUI\BUTTON` and `GUI\MENU` commands respectively. There are no associated variables to the detached menus. Help is available through a Help button. The menu is mapped when the `GUI\GO` command is typed.

The following procedure illustrates how to create a detach menu; it creates a menu bar with 3 pulldown menus and a help button.

```
!
GUI\PANEL "GRAPHIC X-Window interface" PR:GRAPHIC_SIC.HLP /DETACH
!
GUI\MENU  "SIC"
GUI\BUTTON "SIC\PAUSE" PAUSE
GUI\BUTTON "SIC\CONTINUE" CONTINUE
GUI\BUTTON "SIC\QUIT" QUIT
GUI\BUTTON "SIC\NEXT" NEXT
GUI\BUTTON "SIC\BREAK" BREAK
GUI\BUTTON "SIC\EXIT" "Exit"
!
```

```
GUI\MENU "Graphic"
GUI\BUTTON "DEVICE IMAGE WHITE"  DEVICE
GUI\BUTTON "CLEAR PLOT"    CLEAR
GUI\BUTTON "ZOOM REFRESH"  REFRESH
GUI\BUTTON "ZOOM"          ZOOM
GUI\BUTTON "HARDCOPY /PLOT" HARDCOPY
GUI\MENU /CLOSE
!
GUI\MENU "Program(s)"
GUI\BUTTON "@ PR:X_WHOLE.GRAPHIC"    "Interfero"
GUI\BUTTON "@ PR:X_DISPLAY.GRAPHIC"  "Display"
!
GUI\GO
```

Several detached menus can be activated at once.

2.4.2 Assigning variables in "Window" mode

When the "Main input window" has been created, the LET command behaves in a different way when any of the following options is set: `/PROMPT, /CHOICE, /INDEX, /RANGE, /FILE`

Rather than taking the variable value from the keyboard-typed command line, the LET command has no immediate action, but defines a widget in the "Main input window" (or "Optional window"). This widget will allow the user to define the variable value using the windowing system. 5 types of widgets are available:

- Text widget
  This is the default widget created when option `/PROMPT` is present. The content of the text widget will be used to set the variable.
- Slider widget
  This widget is activated when option `/RANGE` is present. The widget consists both in a numeric area and a slider limited by the given range, and can be used to set a real or integer variable.
- Choice widget
  This widget is activated when option `/CHOICE` is present. The widget consists in a text widget and a pulldown menu containing all specified choices. The user can select its choice with this menu. If the last choice is a "*", any other text can also be entered.
- Index widget
  This widget is activated when option `/INDEX` is present. This widget is similar to the Choice widget, but the returned value is an integer corresponding to the sequence number of the selected choice.
- File widget
  This widget is activated when option `/FILE` is present. The widget consists in a text widget and a file selection widget with the specified file filter.

The "Main input window" is actually created with all defined widgets when command `GUI\GO` is typed.

2.4.3 Actions and Buttons in "Window" mode

The "Main input window" is created when command `GUI\GO` is typed. Four buttons are defined by default:

- the OK button,
  which sets all variables defined in the main *and optional* windows. This button also executes the command passed as argument to the `GUI\GO` command (if specified).
- the UPDATE button,
  which sets all variables defined in the main *and optional* windows, without executing the (optional) command passed as argument to the `GUI\GO` command.

- the ABORT button.
  Variables are not modified, and an error is sent to the main program.

- the HELP button.
  This button displays the help file specified in the `GUI\PANEL` command.

Additional buttons can also be added to the "main window" using the `GUI\BUTTON` command. Two types of buttons exist

- Buttons with no associated parameters. These buttons appear just after the 3 main buttons.
- Buttons with optional parameters. These buttons appear sequentially with the variables, and have an associated parameter or "*optional*" window. When such a button is defined, all subsequent *LET* commands create widget in a "optional" window. This window is by default hidden, but can be unveiled by the user.

The "optional" window provide a way to hide some non-essential parameters, and/or to create a "main window" with a control panel defining many actions, each action having its own input window and separate help.

2.4.4 Help file structure

Command `GUI\PANEL` allows to associate an help file to the main window or detached menus, and command `GUI\BUTTON` does the same for optional windows.

The `HELP` files format should be

```
1 Description
    General help for the window or menu
2 NAME1
    help for variable NAME1
2 NAME2
    help for variable NAME2
1 END
```

where 1 and 2 are in the first column of the text file, and followed by a single space.

Clicking on the HELP button will display the complete help file in a scrolled window. Clicking in the prompt area of an input variable will display the associated variable name and the help for this variable (if it exists).

2.5 Interacting with the Operating System

Since SIC was designed to be portable on various operating systems (currently VMS, Unix, Mac-OS, MS-Windows), interaction with the operating system is normally kept to a minimum.

However, many operations eventually deal with files handled by the operating system. To avoid platform dependencies, SIC allows some basic file operations through the `SIC` command.

When control is desired at the operating system level, the command `SYSTEM` can be used to access it without loosing the SIC context. For user convenience, SIC also accepts the short-cut

```
$ operating_system command
```

instead of the more conventional SIC-like syntax

```
SYSTEM "operating_system command"
```

2.5.1 File Operations

Operations on the file system can be done directly within SIC.

`SIC> SIC DIRECTORY [NewDir]`
controls the working directory. Without argument, the current working directory is listed. With one argument, the working directory is changed. Standard Unix syntax applies to change the working directory.

`SIC> SIC\SIC COPY FileIn FileOut`
Copies file `FileIn` to `FileOut`. Standard SIC file naming convention applies.

`SIC> SIC\SIC DELETE File`
Deletes file named `File`. Caution: no confirmation is required.

`SIC> SIC\SIC RENAME FileOld FileNew`
Renames file `FileOld` to `FileNew`. Standard SIC file naming convention applies. Both files should reside on the same disk. To move files across different disks, use `SIC COPY` and `SIC DELETE`.

The file operations through the SIC command should be used preferentially to operations through the `SYSTEM` command for portability, specially in command procedures.

2.5.2 SYSTEM command: VMS Version

`SYSTEM ["Command"]`
`SYSTEM /PROCESS Process_Name`
The recommended use of the `SYSTEM` command is without any argument. In this case, **SIC** either creates a sub-process or attaches the terminal to a sub-process previously created. The created sub-process has originally the prompt $$. To return to the **SIC** monitor, type `QUIT`. Next `SYSTEM` commands will attach to the same sub-process which is not deleted when the program using **SIC** stops. It is recommended to use this form, rather than the command with argument, because it avoids the overhead of creating one sub-process per command. The sub-process is just created once.

Before attempting a new process creation, **SIC** identifies the existing subprocesses, and prompts you to which one you want to attach. Press the `RETURN` key if you want to create a new one.

In addition, you can attach to other processes created by other programs or commands using the `SYSTEM /PROCESS` command. In this case, to return to **SIC** you have to issue a `VMS` command `ATTACH Prcnam` where Prcnam is the name of the process which is running **SIC** (Use the `VMS` command `SHOW PROCESS /SUBPROCESS` to determine the process name Prcnam). `QUIT` will usually not work (although it may).

With arguments, the `SYSTEM` command effectively activates any valid `VAX-VMS` command by creating a temporary sub-process executing the requested command. Control is returned to `SIC` after completion of the command. This mode is not recommended because of the overhead required to create the process. For example you may issue the command

```
SIC> SYSTEM DIR
```

to list your current directory. Note that you cannot modify a local assignation in this way because of the specificities of the sub-process. Quotes are usually not necessary to delimitate the command passed to `VMS`; the only exception concerns the options, for which you *must* avoid confusion between **SIC** and `SYSTEM`.

```
SIC> SYSTEM "DIR /FULL *.PRO"    is perfectly valid
SIC> SYSTEM DIR /FULL *.PRO       will produce the message

E-INTER,  Unknown option /FULL for command SYSTEM
```

2.5.3 SYSTEM Command: Unix operating system

`SYSTEM ["Command"]`

Without argument, the `SYSTEM` command will create a subshell, using the user's default shell (sh, csh, ksh, etc...). Control will return to the calling program once the subshell terminates (i.e. using the 'exit' or 'bye' or 'logout' command).

With an argument, the `SYSTEM` command will execute the corresponding Unix command in a subshell.

Note that because subshells are used, you cannot change environment variables in this way. In particular, to change your working directory use the `SIC DIRECTORY` command.

2.6 Customizing

2.6.1 Logical Names

All programs based on **SIC** read in files specifying *Logical names* which are used when **SIC**must refer to external files (such as procedure or images). *Logical names* are similar in syntax and functions to VMS logical names. Two files define general logical names required for **SIC** based programs to work properly (where to find help files for example) and site-specific features (such as printer name, scratch space, etc...).

On UNIX and Mac-OS systems, users can specify there own logical names in the file

```
$HOME/.gag.dico
```

On MS-Windows systems, "personal" logical names should be set in the file

```
$GILDAS\dico.lcl
```

where `$GILDAS` is the top directory of the Gildas software as defined at installation (normally `\Program_file\Iram\Gildas` see in the `autoexec.bat` file on Windows-95).

On VMS systems, standard VMS logical names are used.

Logical names can also be added or modified at run time using the `SIC LOGICAL` command.

2.6.2 User Defined Commands

SIC allows the user to define new command, by means of the `DEFINE COMMAND` command. The syntax is the following:

```
DEFINE COMMAND Newcom "Old Command with arguments" [Help_File]
```

where `NEWCOM` is the name of the new command and `HELP_FILE` is an optional text file used to provide help about the command. Because `DEFINE COMMAND` does not provide any specific syntax to specify the use of the new command arguments, it is in practice used essentially to allow documented access to procedures, as for example in

```
DEFINE COMMAND INPUT "@ PR:P_INPUT.GRAPHIC" PR:INPUT_GRAPHIC.HLP
```

2.6.3 Initialization File

Although this is not a default feature of **SIC**, many programs using **SIC** call a initialization macro at run time to define symbols, execute startup commands and so on. This file is typically named

```
GAG_INIT:INIT.DefExt
```

where `DefExt` is the default macro extension used by the program, and is usually the program name. Consult the specific programs documentation. `GAG_INIT` is a *logical name* that normally points to your login directory.

2.6.4 The SIC Command

The `SIC` command controls several internal parameters of the **SIC** monitor.

`SIC> SIC EDIT [ON] [OFF] [Editor_Name]`
Controls whether line edition is possible or not, or select the default text editor. On VMS, use EDT or TPU (Vax Text Processing Utility). On Unix, use `"vi"` or `"emacs"` or any other you wish (note the distinction between lowercase and uppercase). On Unix with the X-Window system, specifying `"emacs &"` will allow to launch the editor in a separate window.

`SIC> SIC VERIFY [ON] [OFF]`
controls the listing of the command flow. Commands executed in procedure mode (macro or loop) will be echoed to the terminal if `VERIFY` is `ON`, and will not be echoed if is `OFF`.

`SIC> SIC MEMORY [ON] [OFF]`
allows to activate or deactivate automatic insertion of commands executed in interactive mode.

`SIC> SIC Language[\] [ON] [OFF]` allows to activate or deactivate one of the current languages of the program. Commands of inactive languages are not scanned by the **SIC** monitor. Language SIC\ itself cannot be deactivated of course.

`SIC> SIC HELP [PAGE|SCROLL|CONTENT|INDEX]`
controls the `HELP` mode.

- SCROLL scroll simple help
- PAGE type simple help, with a prompt to the user for continuation after about 20 lines have been typed.
- CONTENT Display PostScript documentation about the command on X-Window systems
- INDEX Display first reference to the command in the PostScript manual on X-Window systems.

`SIC> SIC PRECISION [SINGLE] [DOUBLE] [AUTO]`
controls the precision in which mathematic formulae are evaluated. Automatic precision uses the precision of the result.

`SIC> SIC EXTENSION [.Defext]`
controls the default macro extension.

`SIC> SIC OUTPUT [FileName]` can be used to redirect the output of command `SAY` to the specified `FileName`. Without argument, the current `SAY` output file is closed.

`SIC> SIC LOGICAL LogName [Translation]` can be used to list, define or redefine logical names Without argument, all logical names are displayed.

The `SIC` command without arguments produces a summary of the internal **SIC** status, and with a single argument it shows the status of that argument.

3 SIC Language Internal Help

3.1 ACCEPT

```
[SIC\]ACCEPT Var_Name /ARRAY File_Name [/options ]
[SIC\]ACCEPT Var_Name /BINARY File_Name Offset
[SIC\]ACCEPT Var_1 [Var_2 [...]] /COLUMN File_Name [/options]
```

Read SIC variables from formatted or binary files. This command has 3 major modes: /ARRAY to read in a FORMATTED way a SINGLE n-dimensional variable, /BINARY to read in BINARY form a SINGLE n-dimensional variable, and /COLUMN to read in a FORMATTED way SEVERAL 1-dimensional variables.

3.1.1 ACCEPT /ARRAY

[SIC\]ACCEPT Var_Name /ARRAY File_Name [/FORMAT String] [/LINE Begin End]

Read a N-Dimensional variable of name Var_Name from a formatted file File_Name, using list-directed (free) format, or a user specified format if /FORMAT option is present. The /LINE option can be used to skip some lines before starting reading. Not recommended for character arrays.

3.1.2 ACCEPT /BINARY

```
[SIC\]ACCEPT Var_Name /BINARY File_Name [Skip]
```

Read a N-Dimensional variable of name Var_Name from a binary file File_Name. The optional Skip argument indicates how many BYTEs to skip before starting reading.

3.1.3 ACCEPT /COLUMN

[SIC\]ACCEPT Var_1 [Var_2 [...] /COLUMN File_Name [/FORMAT String] [/LINE Begin End]

Read ONE or SEVERAL 1-Dimensional variables in list-directed (free) format from a formatted file File_Name. Mixing CHARACTER and NUMERIC (REAL, etc...) arrays is not available yet, and only one character array can be read at a time. The user can specify a format using the /FORMAT option, and select a line range using the /LINE option.

A * as an argument of the ACCEPT command indicates a dummy variable used to skip a column in the input file. For example, the command

```
ACCEPT A * B C /COLUMN TEST.DAT
```

reads A,B and C from columns 1,3 and 4 of file TEST.DAT, since the * indicates to skip the second column.

3.1.4 ACCEPT /FORMAT

Specifies a fortran format to read the input file for command ACCEPT

```
/ARRAY or ACCEPT /COLUMN. This option is invalid with /BINARY.  example:
DEFINE CHARACTER CITY*16[44]
DEFINE REAL X[44] Y[44]
ACCEPT X Y /COLUMN "cities.dat" /LINE 4 / FORMAT "20x,F8.3,1x,F8.3"
ACCEPT CITY /COLUMN "cities.dat" /LINE 4 / FORMAT "2x,A16"
```

3.1.5 ACCEPT /LINE

Indicates the line range to be read in the input file for command ACCEPT/ARRAY or ACCEPT/COLUMN. This option is invalid with /BINARY

3.2 @

```
[SIC\]@ Macro_Name [Par1 [Par2 [...]]]
```

Reads commands from macro Macro_Name and executes them. Up to 8 parameters can be given. These parameters will be substituted to the tokens 1, 2, ..., 8 found in the body of the macro, even within character strings (e.g. Par1 for token 1). Default file extension is program dependent (usually the program name, or .pro), and can be changed using command SIC EXTENSION. All commands will be echoed to the terminal when executed if the VERIFY switch is on (See command SIC VERIFY).

Macros (as any other text files) can be edited using a standard text editor (EDT, TPU, EDU or EVE on VMS, Emacs or Vi on Unix, NotePad or WordPad on MS-Windows), by typing command EDIT with the macro file name as argument (see EDIT).

3.3 BEGIN

```
[SIC\]BEGIN Procedure|Help|Data FileName
```

Begins a new Procedure, Help file, or ASCII Data file. All lines until the corresponding END Procedure|Help|Data FileName command is found are considered to be the body of the new file. Such files are located in the directory designated by the logical name GAG_PROC:.

3.4 BREAK

```
[SIC\]BREAK
```

Terminates a loop execution. The two uses of command BREAK are usually

```
    ON ERROR BREAK
    FOR I 1 TO 3 BY 0.5
    ...
    NEXT
or
    LET A = C               ! A is a known variable
    FOR I 1 TO 100 BY 1
    ...
```

```
    IF I+A.EQ.0
        BREAK
    END IF
    NEXT
BREAK differs from QUIT because it does not transmit any error.
```

3.5 COMPUTE

```
    [SIC\]COMPUTE OutVar OPERATION InVar [Parameters]
```

Perform operations or transformations on variables that are not directly supported by the array capabilities of the SIC command interpretor. OutVar is the output variable, InVar the input variable. Outvar must be defined beforehand.

The following operations are available on REAL and DOUBLE_PRECISION arrays, regardless of their nature:

- MAX MIN MEAN RMS SUM PROD
  for which InVar is an array of rank 1 to 4 (a 1-D to 4-D array), and OutVar must be an array of lesser rank (i.e., one or more dimension less than InVar, down to a number), AND of identical shape as InVar for the dimensions in common.
  Example (if A[4,12,2,8] and b[4,12]): "COMPUTE B MAX A"
  Sections, implicit transpositions, etc... permitted by SIC are supported.
- HISTOGRAM
  Example: "COMPUTE outvar HISTOGRAM invar [hmin] [hmax] [bval] [eval]"
  which puts in variable 'outvar' (dimension [n,2]) the histogram of values of n-D variable 'invar', eventually between the cuts 'hmin' and 'hmax', and with blanking values 'bval' and 'eval' (that is, values of the invar array are not taken in account for the histogram if at 'eval' from 'bval'). These Parameters can be absent. One can use '*' to omit any of them.

  The number of bins is dictated by the first dimension of the array min of the 'invar' array. The 'outvar' variable contains the histogram in its first column (outvar[1]) and the corresponding bin value in the second column (outvar[2]).

The following transformations are available:

- FFT+ (Direct Fast Fourier Transform)
- FFT- (Inverse Fast Fourier Transform)
  which accept REAL or COMPLEX parameters. OutVar is a 2-D array with second dimension equals 2, storing respectively the Real and Imaginary part of the (complex) output Fourier transform. By default, InVar is like OutVar, but if parameter REAL is specified InVar is a 1-D array.
- FOURT+ (Direct Fast Fourier Transform)
- FOURT- (Inverse Fast Fourier Transform)
  Which operates on input and output on COMPLEX Arrays of dimension [2,NX,NY]
- COMPLEX

```
    Populates the Real part of  outvar  (complex  variable)  with  invar
    (real).
  - REAL
    outvar = REAL part of invar. Outvar is Real, Invar is Complex .
  - IMAG
    outvar = IMAGE part of invar. Outvar is Real, Invar is Complex.
  - ABS
    outvar = AMPLITUDE (invar). Outvar is Real, Invar is Complex.
  - PHASE
    outvar = PHASE (invar). Outvar is Real, Invar is Complex.
  - CMPMUL as in COMPUTE varout CMPMUL varin1 varin2:
    varout = PRODUCT of Varin1 and Varin2. All complex arrays.
Miscellaneous Operations:
  - DATE as in COMPUTE creation_date DATE filename
    Where 'filename' is a file name and returns  the  last  modification
    date  in the integer variable 'creation_date'. Used in procedures to
    check if file has been changed, etc...
  - GAG_DATE as in COMPUTE idate GAG_DATE "15-DEC-2035"
    stores the date "15-DEC-2035" as  a  modified  Julian  date  in  the
    integer  variable  'idate'.  This  modified  julian  date has little
    meaning outside the rather sparse community of souls gathered around
    the CLASS program, however...
```

3.6 CONTINUE

```
[SIC\]CONTINUE     or     C
```

Resumes loop or macro execution after a PAUSE (explicit or caused by an error or a <^C>). Typing C instead of CONTINUE will always do exactly the same thing. This is the only superior abbreviation installed in SIC.

3.7 SYSTEM

```
[SIC\]SYSTEM ["Command"] [/PROCESS Process_Name]
```

See HELP SYSTEM VMS or HELP SYSTEM UNIX for operating-system dependent help.

3.7.1 SYSTEM VMS

```
[SIC\]SYSTEM ["Command"] [/PROCESS Process_Name]
            VMS Help version
```

Execute the VAX-VMS command specified by Command, or attach or spawns a sub-process.

If specified with an argument, the SYSTEM command tries to execute the requested VMS command by creating a temporary sub-process executing the requested command. Control is returned to SIC after completion of the command and the sub-process deleted. This mode is NOT RECOMMENDED, because it is time consuming.

If no command is specified, the SYSTEM command spawns a sub-process or attaches the terminal to an existing one. The sub-process prompts for SYSTEM commands at the user's terminal, with a $$ prompt to distinguish it from the parent process. Type QUIT to return to SIC. The first time the SYSTEM command is used, the SIC monitor looks for all existing sub-processes and asks the user the name of the sub-process to attach. Anwser by specifying the complete name, or press RETURN to create a new sub-process. If no sub-process is available, the SYSTEM command creates automatically a new one. If a sub-process creation fails, the SYSTEM command identifies your current sub-processes, and prompts you to which one you want to attach. Following executions of the SYSTEM command simply attach to the same sub-process.

Any sub-process created with the SYSTEM command is not deleted when you exit from the program running SIC, so that you may connect to it by VMS command ATTACH later (or by other program using SIC with the SYSTEM command of course). To kill the sub-process, type LOGOUT (in the sub-process !) instead of QUIT to return to SIC. You can also stop your unwanted sub-processes (from the parent process) by the VMS command
    $ STOP <Sub-process_name>

If the option /PROCESS is specified, the SYSTEM command attaches the terminal to the specified process, which may have been created in any manner. No command is allowed in this case.

3.7.2 SYSTEM UNIX

    [SIC\]SYSTEM ["command name"]
                Unix version

If no argument is given, start a subshell by running the default user shell (sh, csh or ksh). The subshell can be terminated by typing 'exit' or 'bye' or 'logout', depending on Unix version, and controls return to SIC in this case.

If an argument is given, execute the Unix command in a subshell.

Note that new Unix environment variables canot be defined in such a way, since it is a subshell. In particular, use command SIC DIRECTORY to change your working directory.

SHORT CUTS:

Unix commands can also be executed directly from the SIC level using the token, e.g.
    No case conversion occurs in such a case, and the "unix is directly executed in a subshell.

3.8 DEFINE

    [SIC\]DEFINE Type Var1 [Keys...] [Var2 [Keys...] [...]] [/GLOBAL]

```
[/LIKE VarLike]
```

If Type is FUNCTION, define a user-function. If Type is COMMAND, define a new user command. Otherwise, define new variables of the specified type. Type can then be REAL, INTEGER, DOUBLE (for double precision real values), LOGICAL, CHARACTER, or TABLE, HEADER, IMAGE, STRUCTURE or FITS. By default, new variables are LOCAL, i.e. valid only within the current macro and all loops or interactive levels called by this macro. When the /GLOBAL switch is specified, the variables are valid at all levels. Local variables are examined before global variables.

3.8.1 DEFINE CHARACTER

```
[SIC\]DEFINE CHARACTER Var1*N1[DIM1] [...]
```

CHARACTER variables can be scalar or multi-dimensional. The length of CHARACTER variable is specified after an * after the name of the variable. The dimension field (same syntax as for other arrays) should follow the length declaration.

3.8.2 DEFINE COMMAND

```
DEFINE COMMAND  NAME "Equivalent command" [Help_File]
```

defines a new SIC command. The new command will be part of the USER\ language, and will be translated into its equivalent command at execution time. Help_File is an optional argument indicating the name of the associated help text. The standard rules for help syntax applies (see SIC documentation for details). User defined commands appear in the list of command displayed by HELP, and can be abbreviated as normal "program-defined" commands. For example

```
DEFINE COMMAND INPUT "@ input.greg"  pr:inputeg.hlp
```

define a new command USER\INPUT, which will execute procedure input.greg

3.8.3 DEFINE DOUBLE

```
[SIC\]DEFINE DOUBLE Var1[DIM1] [Var2[DIM2] [...]]
```

DOUBLE variables can be multi-dimensional. Up to 4 dimensions can be specified in the optional DIM field, with the following syntax:

```
Var[n1] or Var[n1,n2] etc... up to Var[n1,n2,n3,n4]
```

where Var is the variable name and n1 to n4 are integer constants or variables.

3.8.4 DEFINE FITS

```
DEFINE FITS Var File [/GLOBAL]
```

defines variables associated to the keywords and data of a FITS file. The defined variables depend on the FITS file content. Both "basic" FITS files and FITS extension (XTENSION) are handled.

For basic FITS data, the following variables are defined

VAR%NDIM	Integer	Number of dimensions
VAR%DIM	Integer[4]	Dimensions
VAR%CONVERT	Double[3,4]	Conversion formulae for the 4 axes: Reference pixel, Value at reference pixel, Increment
VAR%DATA	Real	FITS data array

The variables are defined as part of a structure. GreG command LIMITS /RGDATA A recognizes such a basic FITS structure in much the same way as GILDAS images.

The DEFINE FITS command tries to define a SIC structure which contains all FITS keywords, as well as all binary and ASCII tables located in FITS extensions. Support for Random groups (an obsolescent FITS structure) is not implemented.

DEFINE FITS only works to read FITS files, but not to create them.

3.8.5 DEFINE FUNCTION

```
DEFINE FUNCTION NAME(X,Y,Z) Expression(X,Y,Z)
```

defines an arithmetic user function of several variables. The maximum number of variables is 4. The function definition can reference any of the known mathematic operators and intrinsic or program defined functions, but not previously defined user functions (i.e. user function definition is not recursive).

3.8.6 DEFINE HEADER

```
DEFINE HEADER Var1 File1 Key1 [Var2 File2 Key2 [...]] [/GLOBAL]
```

defines variables associated to the HEADER of the GILDAS images located in the specified files. The Keyword must be either READ or WRITE. The following variables are defined:

VAR%GENE	Integer	Length of general section
VAR%NDIM	Integer	Number of dimensions (ReadOnly)
VAR%DIM	Integer[4]	Dimensions (ReadOnly)
VAR%CONVERT	Double[3,4]	Conversion formulae for the 4 axes: Reference pixel, Value at reference pixel, Increment
VAR%BLAN	Integer	Length of blanking section
VAR%BLANK	Real[2]	Blanking and tolerance
VAR%EXTREMA	Integer	Length of extrema section
VAR%MAX	Real	Maximum
VAR%MIN	Real	Minimum
VAR%WHERE	Integer[4,2]	Position of max and min
VAR%DESC	Integer	Length of units and coordinate system secti

VAR%UNIT	Char*12	Image unit
VAR%UNIT1	Char*12	First axis type
VAR%UNIT2	Char*12	Second axis type
VAR%UNIT3	Char*12	Third axis type
VAR%UNIT4	Char*12	Fourth axis type
VAR%SYSTEM	Char*12	Coordinate system
VAR%POSI	Integer	Length of position section
VAR%SOURCE	Char*12	Source name
VAR%RA	Double	Right Ascension
VAR%DEC	Double	Declination
VAR%LII	Double	Galactic longitude
VAR%BII	Double	Galactic latitude
VAR%EPOCH	Real	Epoch of coordinates
VAR%PROJ	Integer	Length of projection section
VAR%PTYPE	Integer	Projection type (code)
VAR%A0	Double	first coordinate of projection center
VAR%D0	Double	second coordinate of projection center
VAR%ANGLE	Double	position angle of projection
VAR%X_AXIS	Integer	First projected axis
VAR%Y_AXIS	Integer	Second projected axis
VAR%SPEC	Integer	Length of spectroscopy section
VAR%LINE	Char*12	Line name
VAR%FREQRES	Double	Frequency resolution
VAR%FREQOFF	Double	Frequency offset
VAR%RESTFRE	Double	Rest Frequency
VAR%VELRES	Real	Velocity resolution
VAR%VELOFF	Real	Velocity offset
VAR%F_AXIS	Integer	Frequency/Velocity axis
VAR%BEAM	Integer	Length of beam section
VAR%MAJOR	Real	Major axis of beam
VAR%MINOR	Real	Minor axis of beam
VAR%PA	Real	Position angle of beam

where VAR is the specified variable name for the header. VAR becomes a dummy variable of type header, which can only be referenced in a further DELETE /VARIABLE command. the VAR\%item variables are ReadOnly or ReadWrite according to the keyword Key, except for the dimension variables, which cannot be modified.

3.8.7 DEFINE IMAGE

```
DEFINE IMAGE Var1 File1 Key1 [Var2 File2 Key2 [...]] [/GLOBAL]
```

defines variables associated to both the content and the header of the GILDAS images located in the specified files. This command acts as a combination of DEFINE HEADER and DEFINE TABLE. It accepts the same keywords (KeyN) as DEFINE TABLE. If the keyword is READ, the header variables are mapped ReadOnly, otherwise they are mapped ReadWrite.

See HELP DEFINE HEADER for a description of the individual header variables.

3.8.8 DEFINE INTEGER

```
[SIC\]DEFINE INTEGER Var1[DIM1] [Var2[DIM2] [...]]
```

INTEGER variables can be multi-dimensional. Up to 4 dimensions can be specified in the optional DIM field, with the following syntax:
    Var[n1] or Var[n1,n2] etc... up to Var[n1,n2,n3,n4]
where Var is the variable name and n1 to n4 are integer constants or variables.

3.8.9 DEFINE LOGICAL

```
[SIC\]DEFINE LOGICAL Var1[DIM1] Var2[DIM2] [...]
```

LOGICAL variables can be multi-dimensional. Up to 4 dimensions can be specified in the optional DIM field, with the following syntax:
    Var[n1] or Var[n1,n2] etc... up to Var[n1,n2,n3,n4]
where Var is the variable name and n1 to n4 are integer constants or variables.

3.8.10 DEFINE REAL

```
[SIC\]DEFINE REAL Var1[DIM1] [Var2[DIM2] [...]]
```

REAL variables can be multi-dimensional. Up to 4 dimensions can be specified in the optional DIM field, with the following syntax:
    Var[n1] or Var[n1,n2] etc... up to Var[n1,n2,n3,n4]
where Var is the variable name and n1 to n4 are integer constants or variables.

3.8.11 DEFINE STRUCTURE

```
DEFINE STRUCTURE Str [/GLOBAL]
```

defines a new structure name. Structure naming follows the Fortran-90 convention, i.e. Str%SubStr%SubStrElement. Structure elements (including sub-structures if needed) can be defined using command
    DEFINE REAL Str%Element
etc...

An entire structure and all its associated members is deleted by a single command DELETE Str /VARIABLE.

3.8.12 DEFINE TABLE

```
DEFINE TABLE Var1 File1 Key1 [Var2 File2 Key2 [...]] [/GLOBAL]
```

defines variables associated to GILDAS images located in the specified file. The variable type and dimensions are derived according to the value of the keyword Key and the file content:
- READ or WRITE: use the type and dimensions from the file, and connect the image in Readonly or ReadWrite access. The variable name

must not include any dimension field.
- DOUBLE, INTEGER or REAL: create a new image of the specified type. The dimensions must then be specified in the dimension field of the variable name, as for a standard variable.
- EXTEND: take type and first dimensions from the file, but extend the last dimension to the value specified in the dimension field. The full syntax in this case is thus
  DEFINE TABLE Var[Ldim] File EXTEND
  where Ldim is the new value for the last dimension.

DEFINE TABLE does not create any additional variables for the image header. See DEFINE IMAGE and DEFINE HEADER for this information.

3.8.13 DEFINE /LIKE

[SIC\]DEFINE Type Var1 [Var2 [...]] /LIKE VarLike

DEFINE IMAGE Var1 File1 Key1 [...]] /LIKE VarLike

The /LIKE option allows definition of Type REAL, LOGICAL, DOUBLE or INTEGER arrays with dimensions identical to those of the (existing) VarLike array. IMAGEs and TABLEs can also be defined in this way. The dimension field must not be specified in such a case.

The /LIKE option is incompatible with the DEFINE FUNCTION and DEFINE HEADER commands.

3.9 DELETE

[SIC\]DELETE [/VARIABLE] [/SYMBOL] [/FUNCTION] Name1 [Name2 [...]]

Deletes specified variables, symbols or functions. For IMAGE variables, also frees the corresponding file.

3.10 EDIT

[SIC\]EDIT [File_Name]

Without argument, EDIT dumps the Stack on a file named STACK.DEFEXT where DEFEXT is the default macro extension specified by the program or by the user using command SIC\SIC EXTENSION, and then calls a text editor to edit this file. If a file name is given, the specified file is editted.

Different editors are available : TPU and EDT on VMS systems, Emacs and Vi on Unix systems, possibly more if your system manager has defined others. The default behaviour is the following :
- On VMS systems, the TPU editor is called, with the default section as defined by logical name TPUSECINI. TPUSECINI usually points to a section using the TPU editor with EDT interface and additional features added by the Groupe d'Astrophysique such as double window

```
    mode, but you may have redefined it to your own section.
  - On Unix systems, Emacs with EDT mode is normally used.
```

The behaviour can be changed using the command SIC EDIT, or specifying at system level a logical name for GAG_EDIT. For example to use the EDT editor, you could type

```
    SIC> SIC EDIT EDT
```

within a program using SIC. EDT will then be used for any EDIT command typed during the program execution. Alternatively, you could define your default SIC editor by, on VMS systems, using the DCL command

```
    DEFINE GAG_EDIT EDT
```

on Unix systems, inserting the following command in your $HOME/.gag.dico file

```
    GAG_EDIT   emacs
```

3.11 ELSE

```
    [SIC\]ELSE [IF Logical_expression [THEN]]
```

Conditional directive in an IF-END IF block. Similar to FORTRAN ELSE and ELSEIF statements, but note that here the space between ELSE and IF is compulsory, while the THEN keyword is optional. If the compulsory space bothers you, just define the following symbol

```
    SYMBOL ELSEIF "SIC\ELSE IF"
```

4 SIC Programming Manual

The **SIC** programming manual has been moved to the **GILDAS** programming guide.

5 SIC Error Messages and Recovery Procedures

SIC may output a number of error messages. These are usually self explanatory, and most of them refer to typing errors, or to an unanticipated degree of complexity reached during the program execution (too many loops, macros, complex mathematic formulas, etc...). More severe errors may appear, usually due to internal logic errors in the calling program. SIC is a relatively safe program. However, its very flexible possibilities, and in particular the possibility of calling it as a command monitor in multi-language application, possibly written independently by different programmers, make it very difficult to be error free. This section list all the error messages written by SIC, and some (but not all) information messages. The format of a SIC message is the following

```
C-FACILITY,  Explanation text
```

C is a letter indicating the severity of the message, and may be :

`I` for Information

`W` for Warning. Normal execution can proceed, but the operation was not completed.

`E` for Error. Something really went wrong, and a corrective action should (usually) take place. Suggested actions are mentioned.

`F` for Fatal Error. This is a programming error, either in SIC, or in the calling program, or an unrecoverable error causing a program abort (such as a `PAUSE` in batch sessions).

`FACILITY` is a mnemonic of the subroutine or of the command where the error occured.

`"Explanation text"` is a concise but usually self explanatory message.

In case of Fatal errors, the "recovery procedure" usually indicates to "Submit an SPR". An SPR is a *Software Performance Report*, and it should be sent to the **SIC** authors, by E-Mail at

```
gildas@iram.fr
```

(`GILDAS` is a reserved account for all **GILDAS** software).

List of Error Messages

5.1 A through C

`E-COMPUTE, TRANSPOSE not implemented`
`SIC, COMPUTE` command. Self explanatory...
User action : If your variables are images, use the `VECTOR\TRANSPOSE` command instead.

`E-COMPUTE, Variable cannot be written`
`SIC, COMPUTE` command. The output variable is defined ReadOnly.
User action : Probably a user error. Check your variable name. If it is what you wanted, it means you are trying to overwrite a protected program defined variable, and this is forbidden of course.

`E-COMPUTE, Variable must be Real`
`SIC, COMPUTE` command. The required actions operate only on Real variables.
User action : Define intermediate variables if necessary.

`E-COMPUTE, Invalid OUTPUT variable dimensions`
`SIC, COMPUTE` command on Fast Fourier Transform action.
User action : See Help.

5.2 D

`E-DECODE, Invalid arithmetic expression`
`SIC`, Argument decoding routines. An arithmetic expression used as argument is invalid. The message is usually preceded by more detailed explanation.
User action : correct the expression. If a message "Internal logic error" appeared, submit an SPR.

`E-DECODE, Invalid logical expression`
`SIC`, Argument decoding routines. A logical expression used as argument is invalid. The message is usually preceded by more detailed explanation.
User action : correct the expression. If a message "Internal logic error" appeared, submit an SPR.

`E-DECODE, Error computing <String>`
`SIC`, Argument decoding routines. Some error occured during evaluation of a valid arithmetic expression. A more detailed text precedes this message. This is usually due to undefined variables, or arithmetic errors like square root of negative values.
User action : correct any typing error. Check values of variables if an arithmetic error occured.

`E-DECODE, Option <Integer> or argument <Integer> out of bounds`
`SIC`, Argument decoding routines. This is a programming error : a command required too many arguments or options.
User action : Notify the programmer who should consult the **SIC** programming manual.

`E-DECODE, You have overwritten the command line pointers.`
`SIC`, Argument decoding routines. This is a programming error: the program tries retrieving an argument after another command line has been analysed. This frequently occurs when **GreG** is called in library mode by another program. This should only be done AFTER all arguments have been retrieved.
User action : Notify the programmer who should retrieve all needed arguments before he starts analysing another line.

`E-DECODE, Missing argument number <Integer> of Command <String>`

`E-DECODE, Missing argument number <Integer> of Option <String>`
`SIC`, Argument decoding routines. The specified argument is mandatory for the command or option.
User action : specify the missing argument.

`E-DEFINE, Cannot specify dimension for existing images`
`SIC, DEFINE or LET /NEW` commands. Dimensions can only be specified when creating an image.
User action : Don't specify a dimension for existing images.

`E-DEFINE, Invalid variable name <String>`
`SIC, DEFINE or LET /NEW` commands. Variable names must be less than 15 characters and begin with a letter.
User action : choose a valid name.

`E-DEFINE, Invalid status <String>`
`SIC, DEFINE HEADER` command. The header status can only be Read or Write.
User action : May be you confused `DEFINE IMAGE` and DEFINE HEADER. Correct your typing.

`E-DEFINE, Memory allocation failure`
`SIC, DEFINE or LET /NEW` commands. The memory needed to create the variable could not be obtained from the operating system, due to a shortage of system resources or quota. This message is may be preceded by an operating system error message. On a typical site, this error will only occur if you are using (very) big arrays.
User action : delete any unused variable, clear the plot if any, and then retry. Try to use *images* instead of *arrays*. If this does not work, exit the program, reenter it and retry. If this is not sufficient, consider whether you *really* need such big arrays. If the answer is yes, you might consider asking your system manager to increase the relevant quota.

`E-DEFINE, Missing dimension of new image`
`SIC, DEFINE` command. The dimension of a new image must be specified
User action : specify the dimension.

`E-DEFINE, Only last dimension can be extended`
`SIC, DEFINE` command. The `EXTEND` request is not acceptable.
User action : see `DEFINE IMAGE` internal help.

`E-DEFINE, Syntax error`
`SIC, DEFINE FUNCTION` command. The function definition is invalid.

`E-DEFINE, Too many variables`
`SIC, DEFINE or LET /NEW` commands.
User action : delete some existing variables, or use them instead of defining a new one. If you cannot, ask your system manager about increas **SIC** workspace.

`E-DEFINE, Too many arguments`
`SIC, DEFINE FUNCTION` command. Invalid syntax: only one function definition at a time is possible
User action : use several `DEFINE FUNCTION` commands if necessary.

`E-DEFINE, Variable <String> already exists`
`SIC, DEFINE or LET /NEW` commands. The specified name already is a known variable.
User action : use another name, or use (with command `LET` the already defined variable if you believe you may do so.

`E-DELETE, Incompatible options`
`SIC, DELETE` command. The options `/FUNCTION`, `/SYMBOL` and `/VARIABLE` are mutually exclusive.

`E-DELETE, Missing option`
`SIC, DELETE` command. One of the options `/FUNCTION /SYMBOL` and `/VARIABLE` must be present.

`E-DELETE, No such variable <String> SIC, DELETE` command. The specified variable cannot be deleted because it does not exist.

`E-DELETE, Variable <String> not deleted` SIC, `DELETE` command. The variable could not be deleted, because it is program defined
User action : May be a typing error. Check the variable name.

`E-DIMENSION, Invalid dimension <string>`
Any command with a numerical argument. In the present version of **SIC** indexes of arrays can only be constants or scalar numerical variables. Complex numerical expressions are not allowed.
User action : use an intermediate variable.

`E-DIMENSION, Invalid mixture of implicit and explicit dimensions`
`SIC, LET` command. Implicit loops on arrays cannot be mixed with explicit indexes for other dimensions.
User action : either use an explicit `FOR-NEXT` loop, or rearrange your expression to use the implicit loop (which is *much* faster).

`E-DIMENSION, Invalid string length <Number>`
`SIC, DEFINE or LET /NEW` commands. Character variable is not positive.

`E-DIMENSION, Invalid variable name <string>`
`SIC, DEFINE or LET /NEW` commands. Variable names must be less than 15 characters and begin with a letter.
User action : choose a valid name.

`E-DIMENSION, Missing character size`
`SIC, DEFINE or LET /NEW` commands. The size of character string must be specified.
User action : specify a length.

`E-DIMENSION, Missing closing bracket`
Any command with a numerical argument. An opening bracket is not matched with the corresponding closing bracket.
User action : add the appropriate closing bracket.

`E-DIMENSION, Too many dimensions`
`SIC, DEFINE or LET /NEW` commands. Only 4 dimensions are supported.
User action : decrease the number of dimensions.

5.3 E

`I-EDIT, Using <String> editor`
`SIC, EDIT` command with argument, information message. The specified editor is called to edit the file specified as argument. Control will return to **SIC** after the editing session.

`I-EDIT, Writing stack content on STACK.Ext`
`SIC, EDIT` command without argument, information message. `STACK.Ext`, where `Ext` is the current macro extension, will be edited using current editor.

`E-EDIT, File name too long`
`SIC, EDIT` command. The corresponding file cannot be edited.

`E-ELSE, Invalid argument <String>`
`SIC, ELSE` command was followed by an invalid first argument.
User action : correct typing error. `ELSE` can only have no argument or `IF` as first argument.

`E-ELSE IF, Invalid syntax`
`SIC, ELSE` command with argument `IF`. The only accepted syntaxes for `ELSE IF` are:
`ELSE IF <logical expression>`
and
`ELSE IF <logical expression> THEN`

`I-ERROR, occured in <String> at line <Integer>`

`I-ERROR, occured in Loop <Integer> (<Real>) at Line <Integer>`
SIC, error traceback facility. The message contains traceback of an execution error while executing nested macros, stack or loops. Macro names, loop number and index values are given together with the lines being executed.
User action : If a PAUSE occurred correct the erroneous line, execute it and continue the nested macros execution by command CONTINUE, or abort execution by command SIC\QUIT. If an error recovery command is active, it has been automatically executed before resuming the nested macros execution.

`I-ERROR, occured in Program`
SIC, error traceback facility. An error occurred in subroutine mode.
User action : signal the error to the programmer.

`I-ERROR, occured in Error recovery mode`
SIC, error traceback facility. An error occurred in the error recovery command or procedure. A PAUSE is issued.
User action : correct the erroneous recovery procedure and resume execution.

`F-EVALUATE, Invalid precision <Integer>`
Any command with a numerical argument. This is an internal logic error in the arithmetic processor (or a memory error on your machine!).
User action : Please submit an SPR. If you need the result, try toF modify your expression (reorder, use intermediate variables...).

`F-EVALUATE, Internal logic error`
Any command with a numerical argument. This is an internal error in SIC.
User action : submit an SPR. You can try going around the error by modifying your expression.

`E-EXAMINE, Undefined variable <String>`
SIC, EXAMINE command with an argument. The specified variable does not exist.
User action : check for typing errors.

`F-EXAMINE, Invalid data format, internal logic error`
SIC, EXAMINE command.
User action : Submit an SPR.

`W-EXAMINE, No known variable`
SIC, EXAMINE command without argument. No variable has been defined yet.

5.4 F

`E-FOR, Empty list`
SIC, FOR command. The compilation mode is not entered.
User action : Reenter FOR command with a list of values.

`E-FOR, Incomplete list :`
SIC, FOR command. The invalid list is typed with a pointer to the error.
User action : correct the error.

`E-FOR, Input level too deep`
SIC, FOR command. The execution level is too high, too many macros or loops are nested, the loop cannot be executed.
User action : avoid so deeply nested situations by concatenating all macros in a single one instead of nesting them. Deep nesting (more than 8 execution levels) is almost invariably unnecessary.

`E-FOR, Invalid loop :`
`SIC, FOR` command. The invalid list is typed with a pointer to the error.
User action : correct the error.

`E-FOR, Logical expression is too long`
`SIC, FOR` command with `/WHILE` option. The logical expression specified in the `/WHILE` option is too long to be stored and evaluated.
User action : make it simpler using intermediate variables.

`I-FOR, Loop <Integer> has finished`
`SIC, VERIFY` mode. Information message

`I-FOR, Loop <Integer> is running with index <Real>`
`SIC, VERIFY` mode. Information message.

`W-FOR, Loop <Integer> compilation aborted`
`SIC`, loop compilation mode. This message is typed after a `QUIT` command has been typed to abort a loop compilation.

`E-FOR, Loop buffer overflow`
`SIC`, loop compilation mode. Too many commands were entered in the loop buffers. Loop compilation failed.
User action : Put the remaining commands in a macro, and execute the macro within the loop.

`W-FOR, Line not valid in this context, ignored`
`SIC`, loop compilation. The user attempted to insert an invalid command (such as `HELP, EDIT`) into a loop buffer.
User action : such commands cannot be placed in loops.

`W-FOR, No variable or list`
`SIC, FOR` command. Either the loop variable or the list of values is missing.
User action : Correct the command line.

`E-FOR, Only <Integer> levels of FOR - NEXT loops`
`SIC, FOR` command. The user attempt to nest too many loops.
User action : find another solution to your problem than nesting so many loops.

`E-FOR, Syntax error in list :`
`SIC, FOR` command. The invalid list is typed with a pointer to the error.
User action : correct the error.

`E-FOR, Too many arguments in list`
`SIC, FOR` command. The `FOR` list is too long.
User action : Run two (or more) consecutive loops with part of the list to span all values in your original list.

`E-FUNCTION, Invalid function name <string>`
`SIC`, function definition routine. A user program defined function has an invalid name. Function names are limited to 15 characters and must begin with a letter. This is a programming error.
User action : notify the programmer.

`F-FUNCTION, SIC is not loaded`
`SIC`, function definition routine. The program tries to define a function before **SIC** has been initialized. This is a programming error.
User action : notify the programmer.

`E-FUNCTION, Too many arguments to function`
`SIC`, function definition routine. A user program defined function has too many arguments. Function cannot have more than 4 arguments. This is a programming error.
User action : notify the programmer.

`E-FUNCTION, Too many functions`
SIC, function definition routine. The program attempts to define too many user functions. This is a programming error.
User action : notify the programmer who should contact the authors if he really needs so many functions.

`E-FUNCTION, <Integer> arguments to function <String>`
SIC, function definition routine. A user defined function has a negative number of arguments. This is a programming error.
User action : notify the programmer.

5.5 G

`E-GETCOM, Line too long, buffer overflow`
SIC, command reading routine. The command line is too long for the internal buffer.
User action : make it shorter if possible. If not, ask the programmer to increase the line buffer size and relink the program. (Maximum line length in **SIC** is 2048 characters, so we hardly think you may be limited by this).

`E-GETCOM, Read error on macro file, unit <Number>`
SIC, command reading routine. An error occured while reading command from a macro.
User action : this is most likely due to a hardware problem, unless you are attempting to read a binary file... Check the macro. Type the macro to see what command could not be read, execute it and resume macro execution.

5.6 H

`W-HELP, Error opening <String>`
SIC, HELP command. The Help file for a language does not exist.
User action : check with the programmer or system manager that all logical names have been correctly defined.

`W-HELP, Language <String> is in library only mode`
SIC, HELP command. The specified language is in library mode, no help is available for it.
User action : commands from this language cannot be accessed interactively, except by specifying the full language name.

`W-HELP, No help for <String>`
SIC, HELP command. The specified command ¡String¿ is not documented.
User action : unless you are quite sure of their behaviour (or you like risks) avoid using those undocumented commands.

5.7 I

`E-IF, Invalid syntax`
SIC, IF command. The second argument of the command (if present) was not THEN.

`E-IMPLICIT, Invalid variable name <string>`
SIC, LET command. A variable used in the implicit loop has an invalid name. Variable names must be shorter than 15 characters and begin with a letter.
User action : Use a valid variable name.

`E-IMPLICIT, Too many variables`
SIC, LET command. The total number of variables defined exceeds the SIC limit. Temporary variables used in implicit loops are included in this count.
User action : Delete a few useless variables and retry.

`E-IMPLICIT, Variable already exist`
SIC, LET command. This is an internal logic error.
User action : Submit an SPR. While waiting for the correction, you may try modifying your expression.

`E-INCARNATE, Bad incarnation type`
SIC, type conversion routine. The type conversion routine was called with a non numeric output type. This is a programming error.
User action : Notify the programmer.

`E-INCARNATE, Bad variable type`
SIC, type conversion routine. The type conversion routine was called with a non numeric input type. This is a programming error.
User action : Notify the programmer.

`E-INTER, Ambiguous command, could be :`
SIC, monitor routine. The command name is ambiguous.
User action : specify more characters or specify language to avoid ambiguities.

`E-INTER, Ambiguous option, could be :`
SIC, monitor routine. The option name is ambiguous.
User action : specify more characters.

`W-INTER, No command on line`
SIC, monitor routine. A command line only contained the language field.

`E-INTER, Too many words in line`
SIC, monitor routine. The user program tried to access more than 100 arguments. This is a programming error.
User action : if you really need so many arguments, submit an SPR.

`E-INTER, No options allowed for command <String>`
SIC, monitor routine. The command has no options.
User action : Suppress options from the command line.

`E-INTER, Unbalanced quote count`
SIC, monitor routine. A command line has an odd number of double quotes.
User action : Correct typing mistake and reenter command.

`E-INTER, Unknown command`
SIC, monitor routine. The command does not exist in any active language.
User action : check spelling or bring more languages in the active scope (Command SIC\SIC).

`E-INTER, Unknown command <String> for language <String>`
SIC, monitor routine. The command does not exist in the specified language.
User action : check spelling.

`E-INTER, Unknown language <String>`
SIC, monitor routine. The specified language is not known.
User action : Check spelling. If good, verify you are using the right program.

`E-INTER, Unknown option <String> for command <String>`
SIC, monitor routine. The command has no such option
User action : check spelling.

5.8 J trough L

`F-LET, Cannot assign arrays`
`SIC`, calling program. This is a programming error. The program attempts to assign values to an array through a call to `SIC_LET_REAL` (or `SIC_LET_INTE...`). This is not allowed.
User action : notify the programmer. If you need to assign values to an array, call `SIC_DESCRIPTOR` and do the assignment in your program.

`E-LET, Header structures cannot be assigned`
`SIC, LET` command. The variable to be assigned is a generic header name.
User action : Add the % symbol after the generic header name to assign a header structure.

`E-LET, Invalid attribute <string>`
`SIC, LET /NEW` command. The only recognised attributes for a variable are `GLOBAL` and `LOCAL`.

`E-LET, Memory allocation failure`
`SIC, LET` commands. The memory needed as work space could not be obtained from the operating system, due to a shortage of system resources or quota. This message is preceded by the VMS error message. On a typical site, this error will only occur if you are using (very) big arrays or images.
User action : delete any unused variable, and then retry. If this does not work, exit the program, reenter it and retry. If this is not sufficient, consider whether you *really* need such big arrays. If the answer is yes, you might consider asking your system manager to increase the relevant quota.

`E-LET, Operation not supported on string arrays`
`SIC, LET` command. String arrays cannot be assigned directly.
User action : Define the string arrays element by element, using a loop.

`E-LET, Readonly variables cannot be modified`
`SIC, LET` command. You are attempting to modify a protected variable declared by the program.
User action : this is not allowed. Define another variable if you need temporary storage.

`E-LET, Readonly headers cannot be modified`
`SIC, LET` command. You are attempting to modify a protected header.
User action : This is not allowed. Redefine the header with write access if needed.

`E-LET, Trailing arguments in assignement`
`SIC, LET` command. While trying to use the element by element `LET` command, you omitted or added one argument.
User action : Check the array size, and count the number of arguments.

`E-LET, Undefined header <String>`
`SIC, LET` command. The assigned header is not defined.
User action : Check variable name for typing error.

`E-LET, Undefined variable <String>`
`SIC, LET` command. The assigned variable is not defined.
User action : first check variable name for typing error. If you want to assign a new variable, use `DEFINE` command or option `/NEW` of command `LET` to define it.

`E-LET, Variable type does not match declaration`
`SIC, SIC_LET_xxx` subroutine. This is a programming error. The program attempted to assign a value of wrong type to a defined variable.
User action : notify the programmer.

`E-LOGICAL, Error evaluating <String>`
`SIC`, argument decoding routine. Evaluation of a logical expression failed. This message is usually preceded by a more detailed text indicating why the expression could not be evaluated.
User action : check for undefined variables.

`E-LOGICAL, Invalid logical expression`
SIC, argument decoding routine. An invalid logical expression was found (most likely in an `IF, FOR /WHILE or ELSE IF` command). This message is usually preceded by a more detailed text indicating why the expression is invalid.
User action : correct the expression.

5.9 M

`E-MACRO, Input level too deep`
SIC, `@` command. A macro could not be executed due to an execution level too high.
User action : finish some macro execution before activating this one. Eventually, you may need to rearrange your macros to avoid so many execution levels.

`E-MACRO, Recursive call to macro <String>`
SIC, `@` command. A recursive call occurred to the specified macro.
User action : correct the macros which are causing this problem, recursive calls are prohibited.

`E-MACRO, Unable to open macro <String>`
SIC, `@` command. The macro file could not be opened for read.
User action : check for typing error, and possibly for privilege violation. This message is followed by a second line of text indicating a more precise reason.

`E-MATH, Unmatch Closing bracket`
SIC, Mathematic and logical expression analysis modules.
User action : Correct the typing error.

`E-MATH, Missing operator after string`
SIC, function definition module. The expression is incorrect.
User action : Correct the typing error (misplaced parenthesis normally).

`E-MTH, Arithmetic expression is too complex`
SIC, Mathematic and logical expression analysis modules. The expression could not be analyzed because of complexity.
User action : break it in several expression, using intermediate variables.

`E-MTH, Error in FIND_OPERATOR`

`E-MTH, Error in READ_OPERAND`
SIC, Mathematic and logical expression analysis modules. These message usually follows more specific ones.
User action : In case the other messages require to submit an SPR, please indicate the complete list of error messages from MTH.

`E-MTH, Comparing arrays of inconsistent dimensions`
SIC, Mathematic and logical expression analysis modules. An expression contains an illegal mix of arrays with different dimensions.
User action : You probably got confused with variable names. Correct the expression.

`E-MTH, Comparing non scalar variables`
SIC, Mathematic and logical expression analysis modules. A logical expression attempts to compare by order (.GT. .LT. .GE. and .LE.) two arrays. Such comparisons are invalid.
User action : You probably got confused with variable names. Correct the expression.

`E-MTH, Error reading operand <String>`
SIC, Mathematic and logical expression analysis modules. The corresponding string could not be analyzed.
User action : Correct anay (likely) typing error.

`W-MTH, Free operand in BUILD_TREE`
SIC, Mathematic and logical expression analysis modules. This is an internal logic error. Some work space allocated during evaluation has not been freed correctly. The result is nonetheless correct.
User action : Submit an SPR, with the faulty mathematic formula.

`E-MTH, Inconsistent mixture of Arithmeti, Logical and Character expression`
SIC, Mathematic and logical expression analysis modules. The expression is invalid.
User action : Correct your expression (you got confused about variable types, most likely).

`F-MTH, Internal logic error in <String>`
SIC, Mathematic and logical expression analysis modules. An expression was successfully analyzed, but could not be evaluated because of an internal error in the analysis modules.
User action : Submit an SPR, with the faulty mathematic formula. Simplify your formula, or add parenthesis to avoid possible ambiguities and try again. Eventually break your formula into several consecutive ones.

`F-MTH, Invalid arithmetic formula`
SIC, Mathematic and logical expression analysis modules. The formula is invalid.
User action : Correct it. You may have confused some operators or variables.

`F-MTH, Invalid character string <String>`
SIC, Mathematic and logical expression analysis modules. The character string is invalid (empty string, or missing closing quote (")
User action : Correct it. You may have confused some operators or variables.

`F-MTH, Invalid number of arguments in call to <String>`
SIC, Mathematic and logical expression analysis modules. The function call list is incorrect.
User action : Correct it.

`F-MTH, Invalid syntax`
SIC, Mathematic and logical expression analysis modules. This is an internal logic error. An expression contained only opening parenthesis.
User action : Submit an SPR with the faulty expression.

`E-MTH, Level <Number> should already have been evaluated`
SIC, Mathematic and logical expression analysis modules. This is an internal logic error.
User action : Submit an SPR with the faulty expression.

`E-MTH, Mathematics on arrays of inconsistent dimensions`
SIC, Mathematic and logical expression analysis modules. You are trying to combine arrays with inconsistent dimensions.
User action : Correct the expression.

`E-MTH, Memory allocation failure`
SIC, LET command. Memory needed as work space could not be obtained from the operating system, due to a shortage of system resources or quota. On a typical site, this error will only occur if you are using (very) big arrays.
User action : delete any unused variable, clear the plot if any, and then retry. If this does not work, exit the program, reenter it and retry. If this does not work, try using *images* instead of *arrays*. If this is not sufficient, consider whether you *really* need such big arrays. If the answer is yes, you might consider asking your system manager to increase the relevant quota.

`W-MTH, Missing operand in formula <String>`
SIC, Mathematic and logical expression analysis modules. One operator or function is left without operand after parsing.
User action : Correct the expression.

`E-MTH, Missing operator after closing bracket`
SIC, Mathematic and logical expression analysis modules.
User action : Correct the expression.

`E-MTH, Result type mismatch`
SIC, Mathematic and logical expression analysis modules. You are trying to assign a logical value to a numerical variable or so.
User action : Correct the expression.

`W-MTH, Result was not yet assigned`
SIC, Mathematic and logical expression analysis modules. This is an internal logic error. An expression was successfully analyzed, but could not be evaluated because of an internal error.
User action : Submit an SPR, with the faulty mathematic formula. This is only a warning, and in principle the result should be correct. If not, simplify your formula, or add parenthesis to avoid possible ambiguities and try again. Eventually break your formula into several consecutive ones.

`W-MTH, Scratch operand remaining <integer>`
SIC, Mathematic and logical expression analysis modules. This is an internal logic error. An expression was successfully analyzed, but could not be evaluated because of an internal error.
User action : Submit an SPR, with the faulty mathematic formula. This is only a warning, and in principle the result should be correct. If not, simplify your formula, or add parenthesis to avoid possible ambiguities and try again. Eventually break your formula into several consecutive ones.

`E-MTH, Too many operands`
SIC, Mathematic and logical expression analysis modules. Formula is too complex, and does not fit in the internal buffer.
User action : Simplify your formula, and try again. Use intermediate variables to break your formula into several smaller pieces. If this is a serious limitation to you, submit an SPR, and we will increase the buffer size.

`E-MTH, Too many operands in function call`
SIC, Mathematic and logical expression analysis modules. A function was called with the wrong number of arguments.
User action : Correct the call

`E-MTH, Unknown variable <String>`
SIC, Mathematic and logical expression analysis modules. The parsing module was expecting a variable.
User action : This is presumably due to a typing mistake. Correct your expression.

`E-MTH, Unknown function <String>`
SIC, Mathematic and logical expression analysis modules. The parsing module was expecting a user defined function.
User action : This is presumably due to a typing mistake. Correct your expression.

`E-MTH, Unknown logical or relational operator <String>`
SIC, Mathematic and logical expression analysis modules. The parsing module was expecting an operator.
User action : This is presumably due to a typing mistake. Correct your expression.

5.10 O through R

`E-ON, Unknown argument <String>`
SIC, ON command.
User action : See `HELP ON`.

`E-PARSE, Implicit transposition not yet supported`
SIC, Array dimension parser. The specified array subset is invalid, because it requires an implicit transposition of the array variable.
User action : Read the section upon what array variables.

`E-PARSE, Index <Integer> exceeds dimension <Integer> of <String>`
SIC, Array dimension parser. The specified array subset is invalid, because the arrays size is exceeded
User action : Correct your error.

`E-PARSE, Variable <String> has only '<Integer> dimensions`
SIC, Array dimension parser. The specified array subset is invalid, because the dimension does not exist in the array.
User action : Correct your (typing) error.

`W-PAUSE, <^C> ignored, level too deep`
SIC, monitor routine. The user pressed `<^C>` during a command execution, but the execution level is too high to allow a `PAUSE` to be delivered. The execution continues normally.
User action : None, unless a definite interruption is needed in which case the user might consider typing `<^Y>`...

`W-PAUSE, Error returned by aborted command ignored`
SIC, monitor routine. A `PAUSE` was generated as the result of pressing `<^C>` during a command execution, but the command completed with an error status. The `<^C>` takes precedence over the error to avoid using the error recovery procedure. This message follows a `"I-PAUSE, Generated by pressing <^C>"` message.
User action : As for any pause.

`I-PAUSE, Generated by pressing <^C>`
SIC, monitor routine. A `PAUSE` was generated as the result of pressing `<^C>` during a command execution. The previous command completed normally.
User action : Type any command you want. The interrupted execution level will be restarted by command `CONTINUE`.

`F-PAUSE, Level depth too large`
SIC, monitor routine. An error occured, but no `PAUSE` could be delivered because the input level is already too deep. The program aborts execution with a symbolic stack dump. This error can (in principle) only occur if you are using a set of nested macros as error recovery procedure, and with an invalid command in one of the macros...
User action : Correct error and restart the program. Avoid using such complex error recovery systems.

`F-PAUSE, Session is not interactive`
SIC, monitor routine. An error occured, but no `PAUSE` could be delivered because the session is a batch mode. The program aborts execution with a symbolic stack dump.
User action : correct the invalid command which caused the error and resubmit the job.

`E-RECALL, Command line not found`
SIC, `RECALL` command. No command line in the current stack buffer matches the abbreviation given.
User action : Use the `TYPE` command to see if the line you need does exist. This error may be due to an incorrectly specified language field. See `HELP RECALL`.

`E-RECALL, Non existent line in buffer`
SIC, `RECALL` command. The requested line does not exist in the current stack buffer.
User action : Specify a valid command number.

5.11 S

`E-SEXA, Invalid minute field`
`SIC`, Sexagesimal decoding routine. The minute field is negative, or greater than 60.
User action : Correct typing errors.

`E-SEXA, Invalid second field`
`SIC`, Sexagesimal decoding routine. The minute field is negative, or greater than 60.
User action : Correct typing errors.

`E-SEXA, Syntax error`
`SIC`, Sexagesimal decoding routine. Valid syntaxes for sexagesimal arguments are `+DD.DDD`, `+DD:MM.MMM, and +DD:MM:SS.SSS`.
User action : Correct typing errors.

`W-SIC, Ambiguous keyword, choices are :`
`SIC, SIC` command. The first argument is ambiguous.
User action : specify more characters.

`W-SIC, Cannot change SIC\ language status`
`SIC, SIC` command. Information message : language `SIC\` cannot be removed from the active scope.

`W-SIC, Cannot set HELP mode <String>`
`SIC, SIC` command. The user requested an invalid mode for `HELP`.
User action : specify a valid mode. Valid modes are `PAGE` and `SCROLL`.

`W-SIC, Cannot set <String> language <String2>`
`SIC, SIC` command. Information message : languages can only be `ON` or `OFF`. Library only languages cannot be brought into the active scope.

`E-SIC, Cannot set <String> switch <String2>`
`SIC, SIC` command. The status `<String2>` does not exist for the switch `<String>`
User action : check for typing errors.

`E-SIC, Command invalid in this context <string>`
`SIC`, monitor routine. Command `IF`, `ELSE` and `ENDIF` can only be used in procedures.
User action : use a procedure.

`F-SIC, Commands must be character*12`
`SIC`, initialization routine. The command names are too long or too short. Execution aborts.
User action : notify the programmer.

`F-SIC, Demonstration period exhausted, Call your system manager`

User action : ask your system manager to buy an authorized copy.

`F-SIC, Duplicate language name`
`SIC`, initialization routine. The language name is already used. Execution aborts.
User action : notify the programmer.

`W-SIC, Edit mode requires an ANSII terminal`
`SIC, SIC` command. Information message : the user requested the `EDIT` mode, but is not logged on a `ANSII` (or compatible) video terminal. `EDIT` mode is left `OFF`.

`I-SIC, Editor is <String>`
`SIC, SIC` command. Information message specifying which text editor is used by command `EDIT`.

`I-SIC, HELP mode is <String>`
`SIC, SIC` command. Information message specifying the `HELP` mode.

`W-SIC, Incorrect nesting of IF blocks`
`SIC`, monitor routine. Some `IF` blocks were not properly nested and are still opened when a macro or loop terminates. The opened blocks are closed by **SIC**.
User action : although this is only a warning, it may be wise to check the current macro for possible error(s).

`F-SIC, Initialization error number <Integer>`
`SIC`, initialization routine. An undocumented initialization error occurred. Execution aborts.
User action : notify the programmer, who should submit an SPR.

`F-SIC, Internal logic error LIRE = -1`
`SIC`, command reading routine. This is a fatal bug check.
User action : Submit an SPR, with as much information as you can (log file, program listing, etc...).

`E-SIC, Invalid nesting of loops and IF blocks`
`SIC`, monitor routine. Some `FOR` loops were not properly nested and are still opened when an `IF` block terminates.
User action : Check the current macro for error(s).

`W-SIC, Invalid precision <string>`
`SIC, SIC` command. The only supported precisions are `SINGLE` (or `REAL`) and `DOUBLE`. Previous precision is kept.
User action : specify a valid precision.

`F-SIC, Language initialization failure`
`SIC`, initialization routine. This message is preceded by a more detailed account of the problems. This is a fatal error, and the program execution aborts with a symbolic stack dump.
User action : notify the programmer.

`F-SIC, Programming error: recursive call to SIC`
`SIC`, monitor routine. The programmer made a recursive call to **SIC**. This is a fatal error, and the program execution aborts with a symbolic stack dump.
User action : notify the programmer.

`W-SIC, Session is not interactive, EDIT and MEMORY Off`
`SIC`, monitor routine. Information message. This message appears at the beginning of the program (usually when nobody is available to read it...).

`F-SIC, SIC is not loaded`
`SIC`, monitor routine. The program attempted to use **SIC** before initializing the interpreter. This is a programming error.
User action : notify the programmer.

`I-SIC, <String> switch is <String2>`
`SIC, SIC` command. Information message.

`I-SIC, <String> language is <String>`
`SIC, SIC` command. Information message.

`W-SIC, Sub-process <String> is still active`
`SIC`, exit routine. A sub-process has been created earlier by the `SYSTEM` command. The sub-process is not deleted.
User action : You can attach to this sub-process at any time by the VMS command `ATTACH`, or delete it by the VMS command `STOP`.

`E-SIC, Too many IF blocks`
`SIC`, monitor routine. You are attempting to nest `IF` blocks too deeply.
User action : Do not. Find another way to solve your problem.

`F-SIC, Too many commands and options. This program is only dimensioned for <Integer> user-defined commands.`
SIC, initialization routine. The program has too many commands and options. Execution aborts.
User action : notify the programmer, who may submit an SPR (even though this is no an error in **SIC** just a limitation).

`F-SIC, Too many languages`
SIC, initialization routine. The program has too many languages. Execution aborts.
User action : notify the programmer.

`W-SIC, Undefined character expression <string>`
Formatting routine. The specified string is not a valid character string. This message is usually preceded by other ones that give additional information.
User action : Correct typing mistake(s)

`W-SIC, You are using a demonstration version`
SIC. The version of **SIC** you are using is a demonstration version with a limited validity period (usually 3 to 6 months). Contact the authors about a permanent licence (available at no cost for academic institutions).
User action : Beware that the validity period will expire...

`E-SYMBOL, Invalid symbol name <String>`
SIC, SYMBOL routine. A symbol name must begin with an alphabetic uppercase character.
User action : use a valid name.

`F-SYMBOL, SIC is not loaded`
SIC, DEFINE_SYMBOL routine. The program attempts to define a symbol before SIC has been initialized. This is a programming error.
User action : notify the programmer.

`E-SYMBOL, String too long, translation failed`
SIC, monitor routine. The line buffer is too short to accomodate the symbol translation. The command is not executed, and an error occurs.
User action : : If possible shorten your command or symbol translation. Eventually contact the programmer.

`E-SYMBOL, Symbol definition too long`
SIC, SYMBOL command. The equivalence name is too long. The symbol is undefined.
User action : cut the definition in two symbols and use concatenation when translation is required.

`W-SYMBOL, Symbol name too long <String>`
SIC, SYMBOL command. Symbol names must be shorter than 12 characters.
User action : use shorter symbol names.

`W-SYMBOL, Symbol truncated to <String>`
SIC, SYMBOL command. A symbol name contained more than 12 characters and has been truncated.

`E-SYMBOL, Too many symbols`
SIC, SYMBOL routine. There are too many symbols, the new definition has not been added.
User action : delete unwanted symbols before adding a new one.

`I-SYMBOL, Table is empty`
SIC, SYMBOL command. Information message, there are no symbols defined.

`I-SYMBOL, Table contains :`
SIC, SYMBOL command. Information message, followed by the list of symbols and equivalence strings.

`W-SYMBOL, Undefined symbol <String>`
SIC, SYMBOL command. The specified symbol is undefined.

`E-SYSTEM, Sub-process cannot be activated`
`SIC, SYSTEM` command with or without arguments. The sub-process could not be created because of lack of system resources. The VMS error message follows this error.
User action : If the command had an argument, retry it without as you may connect to an existing subprocess. If this fails, it is generally due to an exceeded quota of subprocesses. If you have other subprocesses running, the `SYSTEM` command lists the current subprocesses and prompts you to which one you want to attach. If none is available, the `SYSTEM` command will return you an error.

`E-SYSTEM, Sub-process <String> could not be attached`
`SIC, SYSTEM` command without argument, or with option `/PROCESS.` The programs failed to attach to an existing sub-process, previously created by the `SIC\SYSTEM` command, or by another program. If the option `/PROCESS` was not present, the command will try to create a new one.
User action : Check process name in case you used the `/PROCESS` option.

`W-SYSTEM, More than <number> sub-processes active`
`SIC, SYSTEM` command with or without arguments. You have reached the maximum number of sub-processes allowed within **SIC**.
User action : If the command had an argument, retry it without as you may connect to an existing subprocess. If this fails, the `SYSTEM` command lists the current subprocesses and prompts you to which one you want to attach. If none is available, the `SYSTEM` command will return you an error.

`E-SYSTEM, Sub-process cannot be created`
`SIC, SYSTEM` command with or without arguments. The sub-process cannot be created, usually because of lack of system resources. The VMS error message follows this error.
User action : If the command had an argument, retry it without as you may connect to an existing subprocess. If this fails, it is generally due to an exceeded quota of subprocesses. If you have other subprocesses running, the `SYSTEM` command lists the current subprocesses and prompts you to which one you want to attach. If none is available, the `SYSTEM` command will return you an error.

5.12 T

`E-TYPE, Cannot open <String>`
`SIC, TYPE` command. The specified file or macro could not be opened. This message is followed by a more precise reason.
User action : check for typing errors.

`E-TYPE, Error reading <String>`
`SIC, TYPE` command. A read error occured during the typing of a file or macro. The `TYPE` command aborts.
User action : most likely you are trying to type a binary file or something like this... Otherwise, it is a hardware problem. Notify your system manager.

5.13 U through Z

`E-VARIABLE, Internal error, no back pointer`
`SIC, DELETE /VARIABLE` command. This is an internal logic error.
User action : Submit an SPR.

`E-VARIABLE, Invalid variable name <String>`
`SIC, DEFINE LET /NEW or FOR` commands. Variable names must be at most 15 characters and begin with a letter.
User action : use a valid name.

`E-VARIABLE, Program defined variables are protected`
`SIC, DELETE /VARIABLE` command. You attempt to delete a variable that has been created by program. This is not allowed.

`F-VARIABLE, SIC is not loaded`
Calling program. The program attempts to define variables before the interpreter has been initialized. This is a programming error.
User action : notify the programmer.

`E-VARIABLE, Too many variables`
`SIC, SIC, DEFINE LET /NEW or FOR` commands. You attempted to define too many variables.
User action : Delete unused variables and retry. If this is not sufficient, submit an SPR, and we will increase the buffer size.

`E-VARIABLE, Variable <String> already exists`
`SIC, DEFINE or LET /NEW`. The specified name is already a known variable.
User action : use a different name, or delete the variable before.

`E-VARIABLE, Variable name too long`
`SIC, DEFINE LET /NEW or FOR` commands. Variable names must be at most 15 characters.
User action : use a shorter name.

`E-ZCRONGNEUGNEU, j'y arrive pas`
Congratulations, **you got a free bottle of champagne** if...
you can reproduce the error.
User action : Contact the authors.

Index

ACCEPT, 14, 24
    /ARRAY, 14, 24
    /BINARY, 14, 24
    /COLUMN, 14, 24
    /FORMAT, 24
    /LINE, 25

BEGIN, 25
BREAK, 16, 25

COMPUTE, 26, 37
CONTINUE, 16, 17, 27

DEFINE, 8, 28
    /LIKE, 33
    CHARACTER, 29
    COMMAND, 22, 29
    DOUBLE, 29
    FITS, 29
    FUNCTION, 30
    HEADER, 12, 30
    IMAGE, 12, 31, 38
    INTEGER, 32
    LOGICAL, 32
    REAL, 32
    STRUCTURE, 32
    TABLE, 12, 32
DELETE, 33
    /SYMBOL, 8
    /VARIABLE, 13

EDIT, 6, 33
ELSE, 15, 34
ELSE IF, 15
ENDIF, 15
EXAMINE, 8, 14
    /FUNCTION, 9
EXIT, 17

FOR, 15
    /WHILE, 15

GUI Mode, 18
GUI$E30F$BUTTON, 18, 20
GUI$E30F$GO, 18, 19
GUI$E30F$MENU, 18
GUI$E30F$PANEL, 18, 20
    /DETACH, 18

HELP, 5, 6

IF, 15

LET, 8, 13
    /CHOICE, 19
    /FILE, 19
    /INDEX, 19
    /LIKE, 11
    /NEW, 8
    /PROMPT, 19
    /RANGE, 19
    /WHERE, 11

Main input window, 18

NEXT, 15, 17

ON ERROR, 17
Optional window, 18

PANEL
    /DETACH, 18
PAUSE, 17

QUIT, 17

RECALL, 6
RETURN, 17
    BASE, 17
    ERROR, 17

SAY, 14, 23
SIC, 20, 23
    COPY, 21
    DELETE, 21
    DIRECTORY, 21, 22
    EDIT, 7, 23
    EXTENSION, 15, 23
    HELP, 23
    LOGICAL, 22, 23
    MEMORY, 23
    OUTPUT, 23
    PRECISION, 8, 23
    RENAME, 21
    VERIFY, 23
SYMBOL, 8
SYSTEM, 20–22, 27
    /PROCESS, 21
    UNIX, 28
    VMS, 27

TYPE, 15